

---

Subject: load average: 0.50, 0.50, 0.38  
Posted by [powervps](#) on Sat, 08 Dec 2007 13:36:35 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

i have a server: Processor : 2 x Dual Processor Quad Core Xeon 5335 8 x 2.00 - real 16 G ram  
load average: 0.50, 0.50, 0.38  
and iam runing only one vps.  
what ican do ?

Quote:ONBOOT="yes"

```
# UBC parameters (in form of barrier:limit)
# Primary parameters
AVNUMPROC="70:80"
NUMPROC="127:192"
NUMTCP SOCK="127:255"
NUMOTHERSOCK="255:300"
VMGUARPAGES="262144:2147483647"
# Secondary parameters
KMEMSIZE="9752512:9936012"
TCPSNDBUF="519488:924288"
TCPRCVBUF="519488:924288"
OTHERSOCKBUF="532096:936896"
DGRAMRCVBUF="332096:332096"
OOMGUARPAGES="6144:2147483647"
# Auxiliary parameters
LOCKEDPAGES="128:128"
SHMPAGES="8192:8192"
PRIVVMPAGES="384000:393212"
NUMFILE="3072:4096"
NUMFLOCK="100:110"
NUMPTY="16:16"
NUMSIGINFO="256:256"
DCACHESIZE="1048576:1097728"
PHYSPAGES="0:2147483647"
NUMIPTENT="128:256"
# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="32048576:32153434"
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
```

---

Subject: Re: load average: 0.50, 0.50, 0.38  
Posted by [powervps](#) on Sun, 09 Dec 2007 00:51:24 GMT

---

[View Forum Message](#) <> [Reply to Message](#)

---

Quote:[root@vps ~]# free -m

```
      total    used    free   shared  buffers   cached
Mem:    16221    7455    8766     0      358    6298
-/+ buffers/cache:    798    15423
Swap:   30718     0    30718
```

and running only one vps

---

---

Subject: Re: load average: 0.50, 0.50, 0.38

Posted by [ugob](#) on Sun, 09 Dec 2007 02:41:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

What is the problem exactly?

---

---

Subject: Re: load average: 0.50, 0.50, 0.38

Posted by [powervps](#) on Sun, 09 Dec 2007 02:47:56 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I am running only one vps and using of real ram 7GB. LolO

I want to know why using so much ram and the vps is only a root with out install any software.

is the problem from my ve-vps.1024.conf-sample

```
root@vps[/email] ~]# vzmemcheck -Av
```

Output values in Mbytes

```
veid    LowMem LowMem  RAM MemSwap MemSwap  Alloc  Alloc  Alloc
      util commit  util  util commit  util commit limit
102     5.73 12.45 122.76 122.76 36.45 248.47 1036.45 1548.43
```

```
-----
Summary:  5.73 12.45 122.76 122.76 36.45 248.47 1036.45 1548.43
          1266.00 1266.00 16221.00 46939.00 46939.00 46939.00 46939.00 46939.00
```

```
[[email]root@vps[/email] ~]# vzcpucheck -v
```

```
VEID      CPUUNITS
```

```
-----
0         1000
```

```
102      1101
```

Current CPU utilization: 2101

Power of the node: 800016

```
[[email]root@vps[/email] ~]#
```

```
[root@vps ~]# vmstat -n 5 5
```

```
procs -----memory----- ---swap-- -----io----- --system-- ----cpu----
 r b swpd free buff cache si so bi bo in cs us sy id wa
 0 0  0 9393336 493668 6227852  0  0  17  86 130  45  1  1 98  0
```

```
[root@vps ~]# free -m
              total    used    free   shared  buffers   cached
Mem:          16221    7048    9172     0      482     6082
-/+ buffers/cache:    484    15737
Swap:         30718     0    30718
[root@vps ~]#
```

Quote:ONBOOT="no"

```
# UBC parameters (in form of barrier:limit)
# Primary parameters
AVNUMPROC="70:80"
NUMPROC="127:192"
NUMTCPSOCK="127:255"
NUMOTHERSOCK="255:300"
VMGUARPAGES="131072:2147483647"
# Secondary parameters
KMEMSIZE="9752512:9936012"
TCPSNDBUF="519488:924288"
TCPRCVBUF="519488:924288"
OTHERSOCKBUF="532096:936896"
DGRAMRCVBUF="332096:332096"
OOMGUARPAGES="6144:2147483647"
# Auxiliary parameters
LOCKEDPAGES="128:128"
SHMPAGES="8192:8192"
PRIVVMPAGES="256000:262140"
NUMFILE="3072:4096"
NUMFLOCK="100:110"
NUMPTY="16:16"
NUMSIGINFO="256:256"
DCACHESIZE="1048576:1097728"
PHYSPAGES="0:2147483647"
NUMIPTENT="128:256"
# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="50048576:50153434"
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
```

---

Subject: Re: load average: 0.50, 0.50, 0.38

Posted by [ugob](#) on Sun, 09 Dec 2007 04:39:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

This is normal.

Please read this, it explains how linux uses memory.

[http://gentoo-wiki.com/FAQ\\_Linux\\_Memory\\_Management](http://gentoo-wiki.com/FAQ_Linux_Memory_Management)

---