
Posted by [azagzin](#) on Tue, 13 May 2008 12:36:50 GMT

[View Forum Message](#) <> [Reply to Message](#)

<http://download.openvz.org/template/precreated/contrib/cento s-5-i386-minimal.tar.gz>

```
azagzin ~ # vzctl start 101
Starting VE ...
Running: /usr/sbin/vzquota show 101
Running: /usr/sbin/vzquota on 101 -r 0 -b 1048676 -B 1153124 -i 200100 -l 220100 -e 0 -n 0 -s 0
Mounting root: /vz/root/101 /vz/private/101
VE is mounted
Unable to set capability: Invalid argument
Unable to set capability
VE start failed
Running: /usr/sbin/vzquota stat 101 -f
Running: vzquota setlimit 101 -b 1048576 -B 1153024 -i 200000 -l 220000 -e 0 -n 0
Running: /usr/sbin/vzquota stat 101 -f
Running: /usr/sbin/vzquota off 101
VE is unmounted
```

```
azagzin ~ # uname -a
Linux azagzin 2.6.24-ovz004 #6 SMP Mon May 12 17:16:54 EEST 2008 i686 Intel(R) Core(TM)2
CPU 6300 @ 1.86GHz GenuineIntel GNU/Linux
```

```
azagzin ~ # cat /proc/self/status
Name: cat
State: R (running)
Tgid: 20108
Pid: 20108
PPid: 18606
TracerPid: 0
Uid: 0 0 0 0
Gid: 0 0 0 0
```

FDSIZE: 256
Groups: 0 1 2 3 4 6 10 11 20 26 27 1006
envID: 0
VPid: 20108
PNState: 0
StopState: 0
VmPeak: 3660 kB
VmSize: 3660 kB
VmLck: 0 kB
VmHWM: 464 kB
VmRSS: 464 kB
VmData: 156 kB
VmStk: 84 kB
VmExe: 28 kB
VmLib: 1316 kB
VmPTE: 16 kB
Threads: 1
SigQ: 0/32607
SigPnd: 0000000000000000
ShdPnd: 0000000000000000
SigBlk: 0000000000000000
SigIgn: 0000000000000000
SigCgt: 0000000000000000
SigSvd: 0000000000000200
CapInh: 0000000000000000
CapPrm: 00000000ffffeff
CapEff: 00000000ffffeff
Cpus_allowed: 00000003
Mems_allowed: 1
voluntary_ctxt_switches: 1
nonvoluntary_ctxt_switches: 0
TaskUB: 0
MMUB: 0

azagzin ~ #cat /etc/vz/conf/101.conf

ONBOOT="no"

UBC parameters (in form of barrier:limit)
KMEMSIZE="11055923:11377049"
LOCKEDPAGES="256:256"
PRIVVMPAGES="65536:69632"
SHMPAGES="21504:21504"
NUMPROC="240:240"
PHYS_PAGES="0:2147483647"
VMGUARDPAGES="33792:2147483647"

```
OOMGUARPAGES="26112:2147483647"  
NUMTCPSOCK="360:360"  
NUMFLOCK="188:206"  
NUMPTY="16:16"  
NUMSIGINFO="256:256"  
TCPSNDBUF="1720320:2703360"  
TCPRCVBUF="1720320:2703360"  
OTHERSOCKBUF="1126080:2097152"  
DGRAMRCVBUF="262144:262144"  
NUMOTHERSOCK="360:360"  
DCACHESIZE="3409920:3624960"  
NUMFILE="9312:9312"  
AVNUMPROC="180:180"  
NUMIPTENT="128:128"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
```

```
DISKSPACE="1048576:1153024"  
DISKINODES="200000:220000"  
QUOTATIME="0"
```

```
# CPU fair sheduler parameter
```

```
CPUUNITS="1000"
```

```
VE_ROOT="/vz/root/$VEID"  
VE_PRIVATE="/vz/private/$VEID"  
OSTEMPLATE="centos-5-i386-minimal"  
ORIGIN_SAMPLE="vps.basic"  
HOSTNAME="centos-vz"  
IP_ADDRESS="x.x.x.x"  
NAMESERVER="x.x.x.x"
```

```
sys-cluster/vzctl-3.0.22
```

```
sys-fs/vzquota-3.0.11
```

File Attachments

1) [2.6.24-ovz004.1.config](#), downloaded 546 times

Posted by [kir](#) on Tue, 13 May 2008 12:41:28 GMT

Posted by [azagzin](#) on Tue, 13 May 2008 13:01:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

In file included from cap.c:25:
/usr/include/linux/capability.h:17:28: error: linux/compiler.h: No such file or directory
In file included from cap.c:25:

cp gentoo-headers-base-2.6.24/include/linux/compiler.h /usr/include/linux/