

---

**Subject:** modprobe fuse problem

**Posted by** Haider **on Tue, 09 Sep 2008 01:33:51 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

i compile & install fuse and sshfs without any problem but when i try to modprobe fuse i get

FATAL: Error inserting fuse

(/lib/modules/2.6.18-92.1.1.el5.028stab057.2/kernel/fs/fuse/ fuse.ko):Operation not permitted  
and when i try to connect through sshfs myserver:/ /mnt/test/ i get /dev/fuse: permission denied  
any solution for these problems?

---

---

**Subject:** Re: modprobe fuse problem

**Posted by** khorenko **on Tue, 09 Sep 2008 06:31:35 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

all modules should be loaded on a Hardware Node (before the Container start in general), you cannot load any modules from inside a Container or that would be a security hole.

--  
Konstantin

---

---

**Subject:** Re: modprobe fuse problem

**Posted by** Haider **on Tue, 09 Sep 2008 14:12:23 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

can u tell me how can i load it on hardware node?? cuz i really really need that module to run

---

---

**Subject:** Re: modprobe fuse problem

**Posted by** khorenko **on Wed, 10 Sep 2008 09:49:48 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

# modprobe fuse

---

---

**Subject:** Re: modprobe fuse problem

**Posted by** Haider **on Wed, 10 Sep 2008 13:29:09 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

the problem is when i run modprobe fuse  
i get

"FATAL: Error inserting fuse

(/lib/modules/2.6.18-92.1.1.el5.028stab057.2/kernel/fs/fuse/ fuse.ko):Operation not permitted"

and

when i try to connect thourgh  
sshfs myserver:/ /mnt/test/  
i get "/dev/fuse: permission denied"

any solution for these problems?

---

---

---

---

**Subject: Re: modprobe fuse problem**

Posted by [khorenko](#) on Wed, 10 Sep 2008 13:38:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

# modprobe fuse

execute this command on a Hardware Node, not inside a Container.

[http://wiki.openvz.org/Hardware\\_node](http://wiki.openvz.org/Hardware_node)

---