
Subject: i very need help i have some problem
Posted by [Nabil taha](#) on Tue, 12 Jan 2010 21:41:22 GMT
[View Forum Message](#) <> [Reply to Message](#)

hello

now i have node

Core2Q 9650 with 8 G Ram , i work on verotal supported on openvz

i have 10 server on that node i see load node : load average: 20.62, 17.49, 13.62

when Run that cmd :

```
vzlist -o vpsid,laverage
  CTID    LAVERAGE
  100 3.99/3.48/2.40
  110 0.07/0.08/0.04
  120 2.33/2.29/1.90
  130 0.03/0.15/0.17
  140 0.62/0.46/0.26
  150 1.17/1.56/1.44
  160 0.35/0.30/0.35
  170 1.62/1.63/1.29
  210 5.63/4.29/2.95
```

enter exp : 210

i see no problem in that vps just some sent mail

i need fix that issue

sec issue :

when run that cmd : vzcpucheck -v

i see error : VEID CPUUNITS

```
-----
ERROR: VE0 CPU units not set, or set too high!
Probably you have not started /etc/init.d/vz
```

plz help me and i sorry i poor in English

Thanks

Subject: Re: i very need help i have some problem
Posted by [dedicados](#) on Wed, 13 Jan 2010 15:26:35 GMT
[View Forum Message](#) <> [Reply to Message](#)

do you try to stop and start openvz???

also a load of 5 is not just for sending emails, maybe a php script is killing the VE, do you use any special panel there?? check the config of the control panel.

Subject: Re: i very need help i have some problem
Posted by [Nabil taha](#) on Wed, 13 Jan 2010 16:54:40 GMT
[View Forum Message](#) <> [Reply to Message](#)

that : OpenVZ Configuration

```
#####  
##                               ##  
##   vePortal Generated OpenVZ   ##  
##   Configuration File         ##  
##                               ##  
#####  
#  
# =====  
# Global Parameters  
# =====  
#  
VIRTUOZZO=yes  
LOCKDIR=/vz/lock  
DUMPPDIR=/vz/dump  
VE0CPUUNITS=1000  
#  
# =====  
# Logging Parameters  
# =====  
#  
LOGGING=yes  
LOGFILE=/var/log/vzctl.log  
LOG_LEVEL=0  
VERBOSE=0  
#  
# =====  
# Disk Quota Parameters  
# =====  
#  
DISK_QUOTA=yes  
VZFASTBOOT=no  
#  
# =====  
# Disable Module Loading  
# if set, vz initscript will not load any modules
```

```
# =====
#
#MODULES_DISABLED=yes
#
# The name of the device whose IP address will be used as source IP for CT.
# By default automatically assigned.
#VE_ROUTE_SRC_DEV="eth0"
#
# Controls which interfaces to send ARP requests and modify APR tables on.
NEIGHBOUR_DEVS=detect
#
# =====
# Template Parameters
# =====
#
TEMPLATE=/vz/template
#
# =====
# Container Default Parameters
# =====
#
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="veportal"
DEF_OSTEMPLATE="centos-5-x86"
#
## Load vzwdog module
VZWDOG="no"
#
## IPv4 iptables kernel modules
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length"
#
## Enable IPv6
IPV6="no"
#
## IPv6 ip6tables kernel modules
IP6TABLES="ip6_tables ip6table_filter ip6table_mangle ip6t_REJECT"
```

and i use panel : Veportal

thanks for help

Subject: Re: i very need help i have some problem
 Posted by [dedicados](#) on Fri, 15 Jan 2010 03:07:48 GMT
[View Forum Message](#) <> [Reply to Message](#)

i mean, if you use a control panel for each VE, check config. also on each VE do a

#top

to see what process is taking a lot of resources

or do it in the main server and you can see wich server and process is doing that.
