
Subject: Container_enter_failed

Posted by [danielmc](#) on Mon, 06 Sep 2010 21:49:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello I found the solution of my problem here

http://wiki.openvz.org/Container_enter_failed

3) Debian : enter the VE manually.

but everyone know how can i automated this command on every host reboot and vm reboot?

I try whit a script in /etc/init.d/ but doesn't work!!

thx

Subject: Re: Container_enter_failed

Posted by [curx](#) on Tue, 07 Sep 2010 15:14:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

is udev running in this container ?

Bye,

Thorsten

Subject: Re: Container_enter_failed

Posted by [danielmc](#) on Tue, 07 Sep 2010 17:51:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

for information :

```
openvz:~# dpkg -l | grep vz
ii  linux-image-2.6.26-2-openvz-686      2.6.26-25          Linux 2.6.26 image on
PPro/Celeron/PII/PIII/P4, OpenVZ support
ii  linux-image-openvz-686                2.6.26+17+lenny1    Linux image on
PPro/Celeron/PII/PIII/P4, OpenVZ support
ii  vzctl                           3.0.22-14          server virtualization solution - control tools
ii  vzquota                         3.0.11-1           server virtualization solution - quota tools
openvz:~# cat /etc/issue
Debian GNU/Linux 5.0 \n \l
openvz:~# cat /vz/private/777/etc/issue
Ubuntu 10.04.1 LTS \n \l
```

I uninstall udev but now my network interfaces are not installed!!!!

I reinstall udev (in cache oufff) no think run why?

openvz:~# vzctl restart 777

Restarting VE

Stopping VE ...

VE was stopped

VE is unmounted

Starting VE ...

VE is mounted

Adding IP address(es): xxxxxxxxxx

Setting CPU units: 10000

Configure meminfo: 135168

Set hostname: xxxxxxxxx

File resolv.conf was modified

VE start in progress...

openvz:~# vzctl enter 777

enter into VE 777 failed

Unable to open pty: No such file or directory

openvz:~# vzctl exec 777 "mount -t devpts devpts /dev/pts"

openvz:~# vzctl enter 777

entered into VE 777

root@mail:/#top

1	root	20	0	2256	1180	992	S	0	0.2	0:00.08	init
28	root	20	0	2164	468	324	S	0	0.1	0:00.00	vzctl
29	root	20	0	2988	1660	1320	S	0	0.3	0:00.00	bash
40	root	20	0	2344	1084	888	R	0	0.2	0:00.02	top

why is nothing running!? I crash my preprod server F***

thx for your help...