

---

Subject: Container\_enter\_failed  
Posted by [danielmc](#) on Mon, 06 Sep 2010 21:49:05 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hello I found the solution of my problem here

[http://wiki.openvz.org/Container\\_enter\\_failed](http://wiki.openvz.org/Container_enter_failed)

3) Debian : enter the VE manually.

but everyone know how can i automated this command on every host reboot and vm reboot?

I try whit a script in /etc/init.d/ but doesn't work!!

thx

---

Subject: Re: Container\_enter\_failed  
Posted by [curx](#) on Tue, 07 Sep 2010 15:14:38 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

is udev running in this container ?

Bye,  
Thorsten

---

Subject: Re: Container\_enter\_failed  
Posted by [danielmc](#) on Tue, 07 Sep 2010 17:51:37 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

for information :

openvz:~# dpkg -l | grep vz

ii	linux-image-2.6.26-2-openvz-686	2.6.26-25	Linux 2.6.26 image on
	PPro/Celeron/PII/PIII/P4, OpenVZ support		

ii	linux-image-openvz-686	2.6.26+17+lenny1	Linux image on
	PPro/Celeron/PII/PIII/P4, OpenVZ support		

ii	vzctl	3.0.22-14	server virtualization solution - control tools
----	-------	-----------	--

ii	vzquota	3.0.11-1	server virtualization solution - quota tools
----	---------	----------	--

openvz:~# cat /etc/issue

Debian GNU/Linux 5.0 \n \l

openvz:~# cat /vz/private/777/etc/issue

Ubuntu 10.04.1 LTS \n \l

I uninstall udev but now my network interfaces are not installed!!!!

I reinstall udev (in cache oufff) no think run why?

```
openvz:~# vzctl restart 777
```

Restarting VE

Stopping VE ...

VE was stopped

VE is unmounted

Starting VE ...

VE is mounted

Adding IP address(es): xxxxxxxxxx

Setting CPU units: 10000

Configure meminfo: 135168

Set hostname: xxxxxxxxxx

File resolv.conf was modified

VE start in progress...

```
openvz:~# vzctl enter 777
```

enter into VE 777 failed

Unable to open pty: No such file or directory

```
openvz:~# vzctl exec 777 "mount -t devpts devpts /dev/pts"
```

```
openvz:~# vzctl enter 777
```

entered into VE 777

```
root@mail:/#top
```

```
1 root    20   0 2256 1180 992 S   0 0.2  0:00.08 init
```

```
28 root    20   0 2164 468 324 S   0 0.1  0:00.00 vzctl
```

```
29 root    20   0 2988 1660 1320 S   0 0.3  0:00.00 bash
```

```
40 root    20   0 2344 1084 888 R   0 0.2  0:00.02 top
```

why is nothing running!? I crash my preprod server F\*\*\*\*

thx for your help...

---