

---

**Subject:** Bootlader

**Posted by** [revhost](#) **on Sat, 26 Mar 2011 10:19:32 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

Hi i changed to openvz on about 6 of my server and one of them that is runnig centos 5.5 i carnt change to bootloader to boot in openvz kernal. Can some one help me with the ssh command and how to do it.

bit of my system info here.

You have a /boot partition. This means that

```
#      all kernel and initrd paths are relative to /boot/, eg.  
#      root (hd0,0)  
#      kernel /vmlinuz-version ro root=/dev/VolGroup01/LogVol00  
#      initrd /initrd-version.img  
#boot=/dev/mapper/pdc_bfiahedhf  
default=1  
timeout=5  
splashimage=(hd0,0)/grub/splash.xpm.gz  
hiddenmenu  
title CentOS (2.6.18-238.5.1.el5.028stab085.3)  
    root (hd0,0)  
    kernel /vmlinuz-2.6.18-238.5.1.el5.028stab085.3 ro root=/dev/VolGroup01/LogVol00 rhgb  
quiet  
    initrd /initrd-2.6.18-238.5.1.el5.028stab085.3.img  
title CentOS (2.6.18-194.32.1.el5xen)  
    root (hd0,0)  
    kernel /xen.gz-2.6.18-194.32.1.el5  
    module /vmlinuz-2.6.18-194.32.1.el5xen ro root=/dev/VolGroup01/LogVol00 rhgb quiet  
    module /initrd-2.6.18-194.32.1.el5xen.img  
title CentOS (2.6.18-194.el5xen)  
    root (hd0,0)  
    kernel /xen.gz-2.6.18-194.el5  
    module /vmlinuz-2.6.18-194.el5xen ro root=/dev/VolGroup01/LogVol00 rhgb quiet  
    module /initrd-2.6.18-194.el5xen.img
```

dont no if i completely cocked it up im new to all this.

thanks.

---

---

**Subject:** Re: Bootlader

**Posted by** [Ales](#) **on Sun, 27 Mar 2011 06:15:47 GMT**

[View Forum Message](#) <> [Reply to Message](#)

---

Change default=1 to default=0 in grub.conf and reboot.

Kernels are counted starting with 0 so if your openvz kernel is the first listed, it should be 0.

---

---

**Subject: Re: Bootlader**

Posted by [revhost](#) on Sun, 27 Mar 2011 11:19:02 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

iv tryed and i still get the error, (not openvz kernal when i try to start openvz)

I've even use kvm over ip to do boot into it and still wont have it

can you tell me how my grub file should be edited please.

thank you ales

---