

---

Subject: Vps Destroy error

Posted by [RoMiONeT](#) on Tue, 24 Feb 2009 15:27:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

i have and error while destroying vps

vps id : 290

i typed vzctl destroy 290

and appeared

vzctl destroy 290

i have created config manually

contain

ONBOOT="yes"

# UBC parameters (in form of barrier:limit)

# Primary parameters

AVNUMPROC="40:40"

NUMPROC="999999:999999"

NUMTCPSOCK="7999992:7999992"

NUMOTHERSOCK="7999992:7999992"

VMGUARPAGES="131072:2147483647"

# Secondary parameters

KMEMSIZE="2147483646:2147483646"

TCPSNDBUF="107374592:289400832"

TCPRCVBUF="107374592:289400832"

OTHERSOCKBUF="107374592:289400832"

DGRAMRCVBUF="107374592:289400832"

OOMGUARPAGES="131072:2147483647"

# Auxiliary parameters

LOCKEDPAGES="999999:999999"

SHMPAGES="131072:131072"

PRIVVMPAGES="131072:131072"

NUMFILE="23999976:23999976"

NUMFLOCK="999999:999999"

NUMPTY="500000:500000"

NUMSIGINFO="999999:999999"

DCACHESIZE="2147483646:2147483646"

PHYSPAGES="0:2147483647"

NUMIPTENT="999999:999999"

# Disk quota parameters (in form of softlimit:hardlimit)

DISKSPACE="20480000:20480000"

DISKINODES="10240000:10240000"

QUOTATIME="0"

```
# CPU fair sheduler parameter
CPUUNITS="1000"
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/280"
OSTEMPLATE="centos-5-i386-afull"
ORIGIN_SAMPLE="vps.basic"
IP_ADDRESS="174.36.246.18 174.36.246.19"
QUOTAUGIDLIMIT="10000"
HOSTNAME="server.zhrra.com"
NAMESERVER="174.36.246.18"
CPULIMIT="800"
MEMINFO="pages:131072"
CPUS="8"
```

and tried to destroy again

vzctl destroy 290

appeared

Destroying container private area: /vz/private/290

Can't move /vz/private/290 -> /vz/vztmp/vzctl-rm-me.XhcHmDg: Operation not permitted

please help me

thanks