

---

Subject: Re: Separate logfile and console loglevel  
Posted by [kfh](#) on Tue, 05 Dec 2006 11:07:10 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

On Tuesday den 5. December 2006 11:47, Igor Sukhih wrote:

> > On Thursday den 30. November 2006 14:59, Dmitry Mishin wrote:

> >>> Separate logfile and console loglevel  
> >>> The separation is implemented as follows  
> >>>  
> >>> 1: split --quite and --verbose from LOG\_LEVEL  
> >>> console loglevel is 0 as default  
> >>  
> >> This patch make sense.  
> >  
> > I worked on the patch, made --verbose accept argument (--verbose=<int>)  
> > Added new parameter VERBOSE=<int> to /etc/vz/vz.conf. Default is 1 if  
> > unset. --verbose alone increments by 1  
> >  
> >>> 2: Make messages more quiet by default  
> >>> logger(0,...) -> logger(1, ...)  
> >>>  
> >>> 3: Make logfile more verbose by default  
> >>> LOG\_LEVEL=2  
> >>  
> >> Why do you need them? For me, it is convinient to see at the VE start,  
> >> which IP it has. It is better, than additional `vzlist` later.  
> >  
> > If I use a script to start 10 VEs, it would be nice to see only partial  
> > info. I could do that with --verbose=0. If one fails I can use  
> > --verbose=2 What do you think about the output below?  
> >  
> > I'm Ok with it the only problem the --verbose option already released  
> > and this is can break already worked scripts.

--verbose still works. It increments current verbose by 1.

If I run:

```
vzctl --verbose=0 --verbose --verbose start 1010  
verbose will be 2 (0 + 1 + 1)
```

> > Regards,

> >

> > Ps.

> > vzquota, /etc/vz/dists/scripts/none and vps-net\_add/vps-net\_del are just

> > "exit 0"

>

> They do exit with error in place error happened.  
I was unclear. My scripts only contains "exit 0".  
I don't know if the standard scripts make any output by default.

> --  
> Igor.  
/Kristian.

---