
Subject: CONFIG_USER_RESOURCE missing?

Posted by [Andreas Mimz](#) on Sat, 31 Mar 2007 18:26:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

I've recently upgraded one of my host servers from an etch 32 bit system to a debian etch 64 bit system (same host)... I've compiled a new kernel using almost the same config like the one I had before (except for 64bit of course)...

Now, when trying to start a VPS I get this message...

VE is mounted

Error: kernel does not support user resources. Please, rebuild with

CONFIG_USER_RESOURCE=y

VE start failed

some parts of my .config:

```
# grep CONFIG_USER_RESOURCE .config
```

```
CONFIG_USER_RESOURCE=y
```

```
CONFIG_USER_RESOURCE_PROC=y
```

```
# egrep "CONFIG_V[EZ]" .config
```

```
CONFIG_VZ_QUOTA=m
```

```
# CONFIG_VZ_QUOTA_UNLOAD is not set
```

```
CONFIG_VZ_QUOTA_UGID=y
```

```
CONFIG_VE=y
```

```
CONFIG_VE_CALLS=m
```

```
CONFIG_VZ_GENCALLS=y
```

```
CONFIG_VE_NETDEV=m
```

```
CONFIG_VE_ETHDEV=m
```

```
CONFIG_VZ_DEV=m
```

```
CONFIG_VE_IPTABLES=y
```

```
CONFIG_VZ_WDOG=m
```

```
CONFIG_VZ_CHECKPOINT=m
```

I'm using a 2.6.18 kernel using the RHEL5 kernel patch 028stab023.1

(that's basically the only other difference to the 32 bit system...

there I was running a 028stab021.1 kernel.).

a strace on 'vzctl start X' shows basically this...

...

...

```
fcntl64(8, F_SETFD, FD_CLOEXEC) = 0
```

```
close(7) = 0
```

```

fcntl64(5, F_SETFD, FD_CLOEXEC)      = 0
close(6)                               = 0
chdir("/var/lib/vz/root/5")           = 0
chroot("/var/lib/vz/root/5")          = 0
setuid()                               = 6432
rt_sigprocmask(SIG_SETMASK, [], NULL, 8) = 0
rt_sigaction(SIGHUP, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGINT, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGQUIT, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGILL, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGTRAP, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGABRT, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGBUS, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGFPE, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGKILL, {SIG_DFL}, NULL, 8) = -1 EINVAL (Invalid argument)
rt_sigaction(SIGUSR1, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGSEGV, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGUSR2, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGPIPE, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGALRM, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGTERM, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGSTKFLT, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGCHLD, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGCONT, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGSTOP, {SIG_DFL}, NULL, 8) = -1 EINVAL (Invalid argument)
rt_sigaction(SIGTSTP, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGTTIN, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGTTOU, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGURG, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGXCPU, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGXFSZ, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGVTALRM, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGPROF, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGWINCH, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGIO, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGPWR, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGSYS, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(SIGRT_2, {SIG_DFL}, NULL, 8) = 0
...
...
...
rt_sigaction(SIGRT_32, {SIG_DFL}, NULL, 8) = 0
rt_sigaction(65, {SIG_DFL}, NULL, 8) = -1 EINVAL (Invalid argument)
syscall_511(0x5, 0x16, 0xbfd26b10, 0xb7fcefd9, 0xb7fe17f8, 0xbfd26ee8,
0xfffffda, 0x7b, 0x7b, 0, 0x33, 0x1ff, 0xb7f
4d172, 0x73, 0x246, 0xbfd26cbc, 0x7b, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0) = -1 (errno 38)
write(2, "Error: kernel does not support u"... , 90) = 90

```

```
write(2, "\n", 1)          = 1
```

Maybe I missed a specific setting when upgrading my kernel using 'make oldconfig' ?!

Has anyone any idea about this?

Thanks alot in advance!

Andreas Mimz
