
Subject: Re: How to setup bonding in a VPS?
Posted by [oviney](#) on Mon, 02 Apr 2007 17:27:22 GMT
[View Forum Message](#) <> [Reply to Message](#)

Ok I did a little more research and found that there is a default package that comes with the RHAS 4 update 4 image. The package is called:

default package -> module-init-tools.i386
openvz package -> dummy-centos-4.i386

By default there isn't a /etc/modprobe.conf file create. I decided to try to hack this a bit and created the file manually and placed the following in it:

```
alias bond0 bonding
options bond0 miimon=100
```

I do notice that if I test the bonding config I get:

```
[root@caotta0008071 ~]# vzctl exec 101 cat /proc/net/bonding/bond0
Ethernet Channel Bonding Driver: v2.6.3 (June 8, 2005)
```

```
Bonding Mode: load balancing (round-robin)
MII Status: down
MII Polling Interval (ms): 0
Up Delay (ms): 0
Down Delay (ms): 0
```

then I look at the message log file:

```
Apr  2 12:26:08 caotta0008071-1 network: Shutting down loopback interface: succeeded
Apr  2 12:26:08 caotta0008071-1 sysctl: net.ipv4.ip_forward = 0
Apr  2 12:26:08 caotta0008071-1 network: Disabling IPv4 packet forwarding: succeeded
Apr  2 12:26:08 caotta0008071-1 network: Setting network parameters: succeeded
Apr  2 12:26:08 caotta0008071-1 network: Bringing up loopback interface: succeeded
Apr  2 12:26:08 caotta0008071-1 network: Bringing up interface bond0: succeeded
```

I am still hunting, but I have not idea at this point why this isn't working as expected.

Any help would be appreciated
