
Subject: Re: VEs with different subnets

Posted by [ugo123](#) on Mon, 02 Jul 2007 12:19:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
titan:/var/lib/vz/template/cache# vzctl create 101 --ostemplate fedora-core-6-i686-default --config vps.basic
```

Creating VE private area (fedora-core-6-i686-default)

Performing postcreate actions

VE private area was created

```
titan:/var/lib/vz/template/cache# vzctl set 101 --onboot yes --save
```

Saved parameters for VE 101

```
titan:/var/lib/vz/template/cache# vzctl set 101 --hostname test --save
```

Saved parameters for VE 101

```
titan:/var/lib/vz/template/cache# vzctl set 101 --ipadd 87.98.196.135 --save
```

Saved parameters for VE 101

```
titan:/var/lib/vz/template/cache# vzctl set 101 --nameserver 194.2.0.50 --save
```

that's how I've created the VZ (just in case).

87.98.196.135, being the public IP address I want to try to assign to the VE.

Here are the parameters that would do the trick if the VE had a "classical" ethernet device :

address 87.98.196.135

netmask 255.255.255.192

network 87.98.196.128

broadcast 87.98.196.191

gateway 87.98.196.129

Here's the output of the commands you've requested. (titan is the HN, test the VE)

```
titan:~# ip a l
```

```
2: bond0: <BROADCAST,MULTICAST,MASTER> mtu 1500 qdisc noop  
   link/ether 00:00:00:00:00:00 brd ff:ff:ff:ff:ff:ff
```

```
4: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue  
   link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00  
   inet 127.0.0.1/8 scope host lo  
   inet6 ::1/128 scope host
```

```
   valid_lft forever preferred_lft forever  
6: eth0: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc pfifo_fast qlen 1000  
   link/ether 00:50:70:26:53:9d brd ff:ff:ff:ff:ff:ff  
   inet 10.1.1.15/16 brd 10.1.255.255 scope global eth0  
   inet6 fe80::250:70ff:fe26:539d/64 scope link  
   valid_lft forever preferred_lft forever
```

```
8: dummy0: <BROADCAST,NOARP> mtu 1500 qdisc noop  
   link/ether 12:62:b8:e1:94:93 brd ff:ff:ff:ff:ff:ff
```

```
10: teql0: <NOARP> mtu 1500 qdisc noop qlen 100  
   link/void
```

```
12: tunl0: <NOARP> mtu 1480 qdisc noop  
   link/ipip 0.0.0.0 brd 0.0.0.0
```

```
14: gre0: <NOARP> mtu 1476 qdisc noop
    link/gre 0.0.0.0 brd 0.0.0.0
16: sit0: <NOARP> mtu 1480 qdisc noop
    link/sit 0.0.0.0 brd 0.0.0.0
18: ip6tnl0: <NOARP> mtu 1460 qdisc noop
    link/tunnel6 00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00 brd
00:00:00:00:00:00:00:00:00:00:00:00:00:00:00:00
1: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue
    link/void
titan:~#
```

```
titan:~# ip r l
87.98.196.135 dev venet0 scope link
10.1.0.0/16 dev eth0 proto kernel scope link src 10.1.1.15
default via 10.1.1.1 dev eth0
titan:~#
```

(10.1.1.1 being my gateway providing NAT Internet access for the HNs, and not the ISP one)

```
titan:~# vzctl exec 101 ip a l
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 16436 qdisc noqueue
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever
3: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,LOWER_UP> mtu 1500 qdisc noqueue
    link/void
    inet 127.0.0.1/32 scope host venet0
    inet 87.98.196.135/32 brd 87.98.196.135 scope global venet0:0
titan:~#
```

```
titan:~# vzctl exec 101 ip r l
192.0.2.0/24 dev venet0 scope host
169.254.0.0/16 dev venet0 scope link
default via 192.0.2.1 dev venet0
titan:~#
```

(I really don't get the 192.0.2.0/24 that I've just seen from the route....)

I can ping from the HN and the VE can ping the HN

```
titan:~# ping 87.98.196.135
PING 87.98.196.135 (87.98.196.135) 56(84) bytes of data.
64 bytes from 87.98.196.135: icmp_seq=1 ttl=64 time=0.063 ms
64 bytes from 87.98.196.135: icmp_seq=2 ttl=64 time=0.017 ms
```

```
[root@test /]# ping 10.1.1.15
PING 10.1.1.15 (10.1.1.15) 56(84) bytes of data.
64 bytes from 10.1.1.15: icmp_seq=1 ttl=64 time=0.061 ms
64 bytes from 10.1.1.15: icmp_seq=2 ttl=64 time=0.017 ms
```

But nothing else, but it's quite logical since I can't set the gateway.... and I don't know how to do it with the venet device....

Just in case, here's the version of the vzctl program

```
titan:~# vzctl
vzctl version 3.0.16-5dso1
Copyright (C) 2000-2007 SWsoft.
This program may be distributed under the terms of the GNU GPL License.
```

Thanks a lot.

Ugo