

---

Subject: Multicast client can't see traffic inside the virtual machine

Posted by [danielcamara](#) on Tue, 17 Jul 2007 10:36:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi people I don't know what, but for sure something I am doing wrong .

I have the following configuration :

```
+=====+ +=====+
| Multicast app | | Multicast app |
++=|  Server  | |  Client  |
|| +-----+ +-----+
|| |  eth0  | |  eth0  |<==++
|| +-----+ +-----+ || | | | |
|| | Virtual Machine | | Virtual Machine | ||
|| |   104   | |   105   | ||
|| +=====+ +=====+ ||
VV      |          |          ||
--||-----||---
||      |          |      XXXX
|| +-----+ +-----+ ||
++==> | veth104.0 | | veth105.0 | ++>=+
++ +-----+ +-----+ ||
||  A          A  || | |
|| |          |  ||
|| | +=====+ |  ||
++==> +----| vzbr0 |----+ ==>=++
      +-----+
      |  eth0  |
      +-----+
      | Real Machine |
      +=====+
```

I have a multicast application that works with broadcast on the address 224.0.0.131. I manage to create the above architecture and pings to both machines, from both machines, work. The three machines, the two virtual and the real one, are in the same network. When I ping the broadcast address, all three machines answer, no problem.

However, when I start the multicast application, in the server, the messages do not reach the eth0 of the client. If I put a tcpdump I can see the messages arriving even at the veth105.0, but not at the eth0 of the Client. Any one has any idea? I followed the how to at <http://wiki.openvz.org/Veth>. I searched through the Internet a little and found that the problem could be in the redirection, so in plus I enabled /proc/sys/net/ipv4/conf/\*/accept\_redirects and /proc/sys/net/ipv4/conf/\*/send\_redirects, and disabled /proc/sys/net/ipv4/icmp\_echo\_ignore\_all and /proc/sys/net/ipv4/icmp\_echo\_ignore\_broadcasts in both, Real Machine and Client machines. However this also didn't work.

Sorry for bother... but I really must this working and it seems to be so close... seems to be just a

configuration or some thing like that, but I really don't have any guesses and I couldn't find more information. Any guesses are welcomed

Best regards...

Daniel Camara

---