
Subject: [PATCH net-2.6.25 4/4][NETNS][RAW]: Create the /proc/net/raw(6) in each namespace.

Posted by Pavel Emelianov on Mon, 14 Jan 2008 13:13:08 GMT

[View Forum Message](#) <> [Reply to Message](#)

To do so, just register the proper subsystem and create files in
->init callbacks.

No other special per-namespace handling for raw sockets is required.

Signed-off-by: Pavel Emelyanov <xemul@openvz.org>

```
net/ipv4/raw.c | 22 ++++++  
net/ipv6/raw.c | 22 ++++++  
2 files changed, 38 insertions(+), 6 deletions(-)
```

```
diff --git a/net/ipv4/raw.c b/net/ipv4/raw.c  
index 206c869..91a5218 100644  
--- a/net/ipv4/raw.c  
+++ b/net/ipv4/raw.c  
@@ -1003,15 +1003,31 @@ static const struct file_operations raw_seq_fops = {  
    .release = seq_release_net,  
};  
  
-int __init raw_proc_init(void)  
+static __net_init int raw_init_net(struct net *net)  
{  
- if (!proc_net_fops_create(&init_net, "raw", S_IRUGO, &raw_seq_fops))  
+ if (!proc_net_fops_create(net, "raw", S_IRUGO, &raw_seq_fops))  
    return -ENOMEM;  
+  
+ return 0;  
}  
  
+static __net_exit void raw_exit_net(struct net *net)  
+{  
+ proc_net_remove(net, "raw");  
+}  
+  
+static __net_initdata struct pernet_operations raw_net_ops = {  
+    .init = raw_init_net,  
+    .exit = raw_exit_net,  
+};  
+  
+int __init raw_proc_init(void)  
+{  
+    return register_pernet_subsys(&raw_net_ops);
```

```

+}
+
void __init raw_proc_exit(void)
{
- proc_net_remove(&init_net, "raw");
+ unregister_pernet_subsys(&raw_net_ops);
}
#endif /* CONFIG_PROC_FS */
diff --git a/net/ipv6/raw.c b/net/ipv6/raw.c
index 970529e..4d88055 100644
--- a/net/ipv6/raw.c
+++ b/net/ipv6/raw.c
@@ -1270,16 +1270,32 @@ static const struct file_operations raw6_seq_fops = {
    .release = seq_release_net,
};

-int __init raw6_proc_init(void)
+static int raw6_init_net(struct net *net)
{
- if (!proc_net_fops_create(&init_net, "raw6", S_IRUGO, &raw6_seq_fops))
+ if (!proc_net_fops_create(net, "raw6", S_IRUGO, &raw6_seq_fops))
    return -ENOMEM;
+
    return 0;
}

+static void raw6_exit_net(struct net *net)
+{
+ proc_net_remove(net, "raw6");
+}
+
+static struct pernet_operations raw6_net_ops = {
+ .init = raw6_init_net,
+ .exit = raw6_exit_net,
+};
+
+int __init raw6_proc_init(void)
+{
+ return register_pernet_subsys(&raw6_net_ops);
+}
+
void raw6_proc_exit(void)
{
- proc_net_remove(&init_net, "raw6");
+ unregister_pernet_subsys(&raw6_net_ops);
}
#endif /* CONFIG_PROC_FS */

```

--

1.5.3.4
