

---

Subject: [ SOLVED ] Pb with multiple identical nfs mount dir in different VEs  
Posted by [mistur](#) on Wed, 16 Apr 2008 08:50:44 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

I have a problem with an identical nfs mount in different VEs

for example, I have inside some VEs :

```
$ df /mnt/data
10.0.0.1:/nfs/data 134148096 43458560 90689536 33% /mnt/data
```

if I perform a reboot on one VE, on all others VEs where this partition is mounted, I got :

```
$ df /mnt/data
10.0.0.1:/nfs/data - - - /mnt/data
```

so the partition is still mount but impossible to do an access on.

at the same time I got this in kernel log on the host :

```
[258012.479557] unregister_vlan_device: ERROR: Tried to remove a non-vlan device with VLAN
code, name: eth1.35 priv_flags: 0
[258012.646468] unregister_vlan_device: ERROR: Tried to remove a non-vlan device with VLAN
code, name: eth1.32 priv_flags: 0
[258013.466439] nfs: RPC call returned error 101
[258013.711497] nfs: RPC call returned error 101
[258013.715907] nfs: RPC call returned error 101
```

As soon as I removed all references of that mount point in all VEs. I can remount it, it's working.

VE 201 :

```
NETIF=" ifname=eth1.32,mac=00:16:3E:02:01:1E,host_ifname=veth201.32,
host_mac=FE:FF:FF:FF:FF:FF;ifname=eth1.35,mac=00:16:3E:02:01
:1E,host_ifname=veth201.35,host_mac=FE:FF:FF:FF:FF:FF;ifname
=eth1.36,mac=00:16:3E:02:01:1E,host_ifname=veth201.36,host_m ac=FE:FF:FF:FF:FF:FF
"NETIF=" ifname=eth1.32,mac=00:16:3E:02:02:1E,host_ifname=veth202.32,
host_mac=FE:FF:FF:FF:FF:FF;ifname=eth1.35,mac=00:16:3E:02:02
:1E,host_ifname=veth202.35,host_mac=FE:FF:FF:FF:FF:FF;ifname
=eth1.36,mac=00:16:3E:02:02:1E,host_ifname=veth202.36,host_m ac=FE:FF:FF:FF:FF:FF "
```

VE 202 :

```
NETIF=" ifname=eth1.32,mac=00:16:3E:02:02:1E,host_ifname=veth202.32,
host_mac=FE:FF:FF:FF:FF:FF;ifname=eth1.35,mac=00:16:3E:02:02
:1E,host_ifname=veth202.35,host_mac=FE:FF:FF:FF:FF:FF;ifname
=eth1.36,mac=00:16:3E:02:02:1E,host_ifname=veth202.36,host_m ac=FE:FF:FF:FF:FF:FF "
```

Ubuntu Dapper 6.06 LTS up to date

```
$ uname -a
```

```
Linux vz01 2.6.18-028stab053 #1 SMP Wed Feb 20 12:15:30 CET 2008 x86_64 GNU/Linux
```

```
$ vzctl --version
```

```
vzctl version 3.0.22
```

if someone has a idea...

thanks

Yoann Moulin