

---

## Subject: Problem with Networking - VENET Interfaces not Configured

Posted by [sjdean](#) on Wed, 04 Jun 2008 16:47:59 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

Im having a few problems with networking.

This is what I see. The VPS venet0 interface doesn't have an IP, and the venet0 doesn't appear to be bridged to the ethernet card on eth1.

The VE doesn't seem to bring up venet0 or venet0:0 (indeed why I have two - Im not sure).

Trying to restart the network services on the VE from the VPS gives:

"Bringing up interface venet0: Error, some other host already uses address 127.0.0.1."

venet0 seems assigned 127.0.0.1 while venet0:0 10.0.0.32 (my chosen ip), which means if it can't bring up venet0 then I would imagine it can't load venet0:0

Even if I change the IP of venet0 on the VE to something unused, it still gives the same error.

What this means, is that I can't ping the IP of 10.0.0.32 from either the network or the VPS.

Here's more info:

Kernel

Quote:Linux rutsey.blargle.local 2.6.24-ovz005.1 #1 SMP Mon May 12 16:38:09 MSD 2008 i  
686 athlon i386 GNU/Linux

Setting IP Address With VZCTL

Quote:Adding IP address(es): 10.0.0.32

SIOCADDRT: No such device

Saved parameters for VE 102

VPS ifconfnig

Quote:venet0 Link encap:UNSPEC HWaddr

00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00

UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

RX packets:0 errors:0 dropped:0 overruns:0 frame:0

TX packets:0 errors:0 dropped:0 overruns:0 carrier:0

collisions:0 txqueuelen:0

RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

VPS Route

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
10.0.0.32	*	255.255.255.255	UH	0	0	0	venet0

## VE Scripts and Files

```
Quote:[root@rutsey sysconfig]# cat network
NETWORKING="yes"
GATEWAY="192.0.2.1"
HOSTNAME="collins.blargle.local"
```

### lo on ve

```
Quote:[root@rutsey network-scripts]# cat ifcfg-lo
DEVICE=lo
IPADDR=127.0.0.1
NETMASK=255.0.0.0
NETWORK=127.0.0.0
# If you're having problems with gated making 127.0.0.0/8 a martian,
# you can change this to something else (255.255.255.255, for example)
BROADCAST=127.255.255.255
ONBOOT=yes
NAME=loopback
```

### venet0 on ve

```
Quote:[root@rutsey network-scripts]# cat ifcfg-venet0
DEVICE=venet0
BOOTPROTO=static
ONBOOT=yes
IPADDR=127.0.0.1
NETMASK=255.255.255.255
BROADCAST=0.0.0.0
```

### venet0:0 on ve

```
Quote:[root@rutsey network-scripts]# cat ifcfg-venet0:0
DEVICE=venet0:0
ONBOOT=yes
IPADDR=10.0.0.32
NETMASK=255.255.255.255
```

## Network Stop

```
Quote:[root@rutsey etc]# vzctl exec 102 service network stop
Shutting down loopback interface: [ OK ]
Cannot find device "sit0"
```

## Network Start

```
Quote:[root@rutsey etc]# vzctl exec 102 service network start
Bringing up loopback interface: Error, some other host already uses address 127.0.0.1.
[FAILED]
Bringing up interface venet0: Error, some other host already uses address 127.0.0.1.
[FAILED]
RTNETLINK answers: File exists
RTNETLINK answers: File exists
RTNETLINK answers: File exists
```

RTNETLINK answers: File exists  
RTNETLINK answers: File exists  
RTNETLINK answers: File exists  
RTNETLINK answers: File exists  
RTNETLINK answers: File exists  
RTNETLINK answers: File exists

Let me know if you need more.

Im trying the fedora-9-i386 template.

Any thoughts?

Cheers  
Simon

---