
Subject: Re: NFS how to export /vz
Posted by [disaster](#) on Fri, 21 Nov 2008 14:28:01 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi!

As i've written all other directories OTHER than /vz DO work fork export with SAME /etc/export only change directoryname.

But here is the file content:

```
/vz 192.168.0.0/255.255.255.0(rw,no_root_squash,sync,no_subtree_check)
```

hosts.deny is empty. Although as i've written nfsd writes: "mountd[19291]: authenticated mount request from 192.168.0.1:729 for /vz (/vz)" if hosts.deny is the problem then it will not write this message.

I do not want to export /vz only a directory in it - but it also does not work for /vz at all.

```
cat /proc/mounts
none /sys sysfs rw 0 0
none /proc proc rw 0 0
udev /dev tmpfs rw 0 0
/dev/sda6 / xfs rw 0 0
/dev/sda6 /dev/.static/dev xfs rw 0 0
tmpfs /lib/init/rw tmpfs rw,nosuid 0 0
tmpfs /dev/shm tmpfs rw,nosuid,nodev 0 0
devpts /dev/pts devpts rw,nosuid,noexec 0 0
/dev/sda5 /boot ext2 rw 0 0
/dev/drbd0 /vz ext3 rw,data=ordered 0 0
nfsd /proc/fs/nfsd nfsd rw 0 0
/vz/private/110 /vz/root/110 simfs rw 0 0
tmpfs /vz/root/110/lib/init/rw tmpfs rw,nosuid 0 0
/proc /vz/root/110/proc proc rw,nosuid,nodev,noexec 0 0
sysfs /vz/root/110/sys sysfs rw,nosuid,nodev,noexec 0 0
varrun /vz/root/110/var/run tmpfs rw,nosuid 0 0
varlock /vz/root/110/var/lock tmpfs rw,nosuid,nodev,noexec 0 0
tmpfs /vz/root/110/dev/shm tmpfs rw,nosuid,nodev 0 0
devpts /vz/root/110/dev/pts devpts rw,nosuid,noexec 0 0
rpc_pipefs /var/lib/nfs/rpc_pipefs rpc_pipefs rw 0 0
```

An strace if rpc.mountd results in some cannot allocate memory:

```
rt_sigaction(SIGALRM, {SIG_DFL}, NULL, 8) = 0
open("/var/lib/nfs/rmtab", O_RDWR) = 11
```


Kernel is: RHEL5 2.6.18-059.6

Stefan
