
Subject: openvz container migration

Posted by [Tommy](#) on Thu, 22 Dec 2011 03:04:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

hi all

I'm doing sth on openvz migration and want to skip the sync time

I put the container's private area on the share storage which both the src node and the des node can access.

then I modify the vzmigrate script simply.

I skip the sync part, umount the private of the container on src node, mount it on des node.

But it sometimes works and sometimes cause INPUT/OUTPUT ERROR!

Does anyone have some cue or suggestion?]

3x

--

Yours Sincerely!

Subject: Re: openvz container migration

Posted by [Andrew Vagin](#) on Tue, 27 Dec 2011 08:55:42 GMT

[View Forum Message](#) <> [Reply to Message](#)

On 12/22/2011 07:04 AM, Tommy wrote:

> hi all

> I'm doing sth on openvz migration and want to skip the sync time

>

> I put the container's private area on the share storage which both the

> src node and the des node can access.

> then I modify the vzmigrate script simply.

> I skip the sync part, umount the private of the container on src node,

> mount it on des node.

> But it sometimes works and sometimes cause INPUT/OUTPUT ERROR!

Who returns INPUT/OUTPUT ERROR? Could you show commands with their output?

Which file system do you use?

Do you use vzquota, is it disabled after umount?

vzctl does lazy umount and it may be the problem.

>

> Does anyone have some cue or suggestion?]

>

> 3x

> --

>

> Yours Sincerely!

>
>
>
>

Subject: sit interface support

Posted by [Antonio Querubin](#) on Sun, 29 Jan 2012 00:55:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

Are sit tunnel interfaces supported in containers? I want to virtualize a tunnel server but the sit interface isn't created. The standard network startup script complains:

Bringing up interface sit1: ioctl: No such device

The host and container are both SL 6.1.

/etc/sysconfig/network-scripts/ifcfg-sit1 looks like:

```
DEVICE=sit1
BOOTPROTO=none
ONBOOT=yes
IPV6INIT=yes
IPV6TUNNELIPV4=x.x.x.x
IPV6TUNNELIPV4LOCAL=y.y.y.y
IPV6ADDR=zzzz:zzzz:zzzz:zzzz::z/126
```

like it does on a real host where sit interfaces work. What am I missing?

Antonio Querubin

e-mail: tony@lavanauts.org

xmpp: antonioquerubin@gmail.com

Subject: Re: sit interface support

Posted by [efball](#) on Sun, 29 Jan 2012 01:48:25 GMT

[View Forum Message](#) <> [Reply to Message](#)

On Sat, Jan 28, 2012 at 02:55:39PM -1000, Antonio Querubin wrote:

```
> Are sit tunnel interfaces supported in containers? I want to
> virtualize a tunnel server but the sit interface isn't created.
> The standard network startup script complains:
>
> Bringing up interface sit1: ioctl: No such device
>
```

> The host and container are both SL 6.1.

You need "tb-tun"

<http://code.google.com/p/tb-tun/>

<http://code.google.com/p/tb-tun/wiki/HOWTO>

I'm using it with a he.net 6to4 IPv6 tunnel.

I put this in /etc/rc.local:

```
setuid /usr/local/sbin/tb_userspace tb 66.220.18.42 xxx.xxx.xxx.xxx sit > /dev/null &  
ifconfig tb up  
ifconfig tb inet6 add 2001:470:x:xxx::2/64  
ifconfig tb mtu 1480  
route -A inet6 add ::/0 dev tb  
ip -6 addr add 2001:470:x:xxx::xxx6 dev tb  
ip -6 addr add 2001:470:x:xxx::xxx3 dev tb
```

I'm using Debian, but SL shouldn't be much different.

--

Frank Ball efball@efball.com
