
Subject: Lost connectivity of VPS after reboot.
Posted by [danl](#) on Tue, 15 Apr 2014 19:46:48 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hello,

I have inherited of a legacy Linux park with most machines running OpenVZ. And it's always been working great. Must I also add that I really enjoy working with your solution? However a problem was brought up to me: some service stopped responding on one of the VPSes.

Before going any further I would like to mention that I have already read both of the following posts without any success.

1. http://columnslashslash.forum.openvz.org/index.php?t=tree&goto=30837&&srch=Unable+to+get+tty+name%3A+Bad+file+descriptor#msg_30837

2. http://columnslashslash.forum.openvz.org/index.php?t=tree&goto=29417&&srch=Unable+to+get+tty+name%3A+Bad+file+descriptor#msg_29417

(PS: You cannot use links until you have posted more than 10 messages. <- message I got when I clicked on "CREATE TOPIC")

Consider the following:

Physical server hosting the OpenVZ service:

Linux HOSTMAXI 2.6.24-29-openvz #1 SMP Tue Oct 11 18:05:43 UTC 2011 x86_64 GNU/Linux

The first conclusion I can draw is that the VPS is missing processes as it's only showing 5 processes running:

```
118      5 running -      HOSTMINI
```

Entering the VPS works fine:

```
root@HOSTMAXI:/# vzctl enter 118
entered into VE 118
root@HOSTMINI:/#
```

However the mounted partitions are clearly shady as it's missing tons of data and possibly other partitions. Also, the system should hold 6Gbs of data:

```
root@HOSTMINI:/# df -h
Filesystem      Size  Used Avail Use% Mounted on
devshm          1003M    0 1003M   0% /dev/shm
root@HOSTMINI:/#
```

Here's the proof of that off HOSTMAXI:

```
root@HOSTMAXI:/vz/private# du 118 -h | tail
68K   118/root/backup/jar_content/org
17M   118/root/backup/jar_content
22M   118/root/backup
4.0K  118/root/.aptitude
8.0K  118/root/.ssh
91M   118/root
4.0K  118/dev/pts
4.0K  118/dev/shm
12K   118/dev
6.0G  118
root@HOSTMAXI:/vz/private#
```

If I look at any other disk usage from any/all of the other running VPS on the same physical host (HOSTMAXI) they'll all look somewhat like this (With the exception of the total size of simfs):

```
root@HOSTMAXI:/vz/private# vzctl enter 114
entered into VE 114
root@HOSTMINI-2:/# df -h
Filesystem      Size  Used Avail Use% Mounted on
simfs           5.0G  914M  4.2G  18% /
tmpfs           1003M  44K  1003M   1% /var/run
tmpfs           1003M   0  1003M   0% /var/lock
devshm          1003M   0  1003M   0% /dev/shm
root@HOSTMINI-2:/#
```

Also, the content of /etc/fstab from that working VPS shows this:

```
root@HOSTMINI-2:/#cat /etc/fstab
# UNCONFIGURED FSTAB FOR BASE SYSTEM
root@HOSTMINI-2:/#
```

However just the the content of HOSTMINI:/etc/fstab (AKA "The broken one") shows the following:

```
# /etc/fstab: static file system information.
#
# <file system> <mount point> <type> <options>          <dump> <pass>
proc            /proc          proc defaults                0      0
```

Before going any further I would like to mention that BCFG2 was disabled around 6 months ago

and those systems were all running perfectly fine ever since. Also, HOSTMINI was working ~1 month ago. At this point I'm suspecting file corruption somewhere, but where?

Let's continue analyzing the faulty VPS and see what other infos I can dig out:

```
root@HOSTMINI:/# runlevel
N 2
root@HOSTMINI:/# ls /etc/rc2.d/
S10syslogd S20archiva S20bcfg2 S20makedev S20postfix S20rsync S20ssh S89cron
S98munin-node S99rc.local S99rmnologin
root@HOSTMINI:/# netstat -noa
Active Internet connections (servers and established)
Proto Recv-Q Send-Q Local Address          Foreign Address         State       Timer
tcp      0      0 10.32.57.76:4949       0.0.0.0:*               LISTEN      off (0.00/0/0)
tcp6     0      0 :::22                  :::*                   LISTEN      off (0.00/0/0)
Active UNIX domain sockets (servers and established)
Proto RefCnt Flags   Type       State      I-Node Path
unix  2      []     DGRAM          29877573 /dev/log
root@HOSTMINI:/# /etc/init.d/ssh stop
* Stopping OpenBSD Secure Shell server...
[ ok ]
root@HOSTMINI:/# /etc/init.d/ssh start
* Starting OpenBSD Secure Shell server...
[ ok ]
root@HOSTMINI:/# netstat -noa
Active Internet connections (servers and established)
Proto Recv-Q Send-Q Local Address          Foreign Address         State       Timer
tcp      0      0 10.32.57.76:4949       0.0.0.0:*               LISTEN      off (0.00/0/0)
tcp6     0      0 :::22                  :::*                   LISTEN      off (0.00/0/0)
Active UNIX domain sockets (servers and established)
Proto RefCnt Flags   Type       State      I-Node Path
unix  2      []     DGRAM          29877573 /dev/log
root@HOSTMINI:/# uname -a
Linux HOSTMINI 2.6.24-29-openvz #1 SMP Tue Oct 11 18:05:43 UTC 2011 i686 GNU/Linux
root@HOSTMINI:/#
```

From what we just saw, SSH port 22 only shows for IPv6 and not for IPv4. Yet, again, that(SSH on port 22 for IPv4) worked last month.

Here's something that also hopefully can help you out as this is sadly too far out of scope for me (for now):

```
root@HOSTMAXI:/etc/vz/conf# strace vzctl enter 118
execve("/usr/sbin/vzctl", ["vzctl", "enter", "118"], [/ 19 vars */]) = 0
brk(0)                               = 0x609000
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696e000
```

```

access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
mmap(NULL, 8192, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696c000
access("/etc/ld.so.preload", R_OK)    = -1 ENOENT (No such file or directory)
open("/usr/lib/tls/x86_64/libvzctl-0.0.2.so", O_RDONLY) = -1 ENOENT (No such file or directory)
stat("/usr/lib/tls/x86_64", 0x7fff32fd1d30) = -1 ENOENT (No such file or directory)
open("/usr/lib/tls/libvzctl-0.0.2.so", O_RDONLY) = -1 ENOENT (No such file or directory)
stat("/usr/lib/tls", 0x7fff32fd1d30)    = -1 ENOENT (No such file or directory)
open("/usr/lib/x86_64/libvzctl-0.0.2.so", O_RDONLY) = -1 ENOENT (No such file or directory)
stat("/usr/lib/x86_64", 0x7fff32fd1d30) = -1 ENOENT (No such file or directory)
open("/usr/lib/libvzctl-0.0.2.so", O_RDONLY) = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\0\0\0\0\3\0>\0\1\0\0\0Ph\0\0\0"..., 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=152536, ...}) = 0
mmap(NULL, 2247848, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) =
0x7f7f9652d000
mprotect(0x7f7f96550000, 2097152, PROT_NONE) = 0
mmap(0x7f7f96750000, 8192, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x23000) = 0x7f7f96750000
close(3)                                = 0
open("/usr/lib/libdl.so.2", O_RDONLY)  = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY)     = 3
fstat(3, {st_mode=S_IFREG|0644, st_size=10919, ...}) = 0
mmap(NULL, 10919, PROT_READ, MAP_PRIVATE, 3, 0) = 0x7f7f96969000
close(3)                                = 0
access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
open("/lib/libdl.so.2", O_RDONLY)      = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\0\0\0\0\3\0>\0\1\0\0\0\16\0\0"..., 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=14624, ...}) = 0
mmap(NULL, 2109728, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) =
0x7f7f96329000
mprotect(0x7f7f9632b000, 2097152, PROT_NONE) = 0
mmap(0x7f7f9652b000, 8192, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x2000) = 0x7f7f9652b000
close(3)                                = 0
open("/usr/lib/libutil.so.1", O_RDONLY) = -1 ENOENT (No such file or directory)
access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
open("/lib/libutil.so.1", O_RDONLY)    = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\0\0\0\0\3\0>\0\1\0\0\0\240\16\0"..., 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=10584, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f96968000
mmap(NULL, 2105624, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) =
0x7f7f96126000
mprotect(0x7f7f96128000, 2093056, PROT_NONE) = 0
mmap(0x7f7f96327000, 8192, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x1000) = 0x7f7f96327000
close(3)                                = 0
open("/usr/lib/libc.so.6", O_RDONLY)   = -1 ENOENT (No such file or directory)

```

```

access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
open("/lib/libc.so.6", O_RDONLY)      = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\0\0\0\3\0>\0\1\0\0\0\340\342"..., 832) = 832
fstat(3, {st_mode=S_IFREG|0755, st_size=1436976, ...}) = 0
mmap(NULL, 3543672, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) =
0x7f7f95dc4000
mprotect(0x7f7f95f1c000, 2097152, PROT_NONE) = 0
mmap(0x7f7f9611c000, 20480, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x158000) = 0x7f7f9611c000
mmap(0x7f7f96121000, 17016, PROT_READ|PROT_WRITE,
MAP_PRIVATE|MAP_FIXED|MAP_ANONYMOUS, -1, 0) = 0x7f7f96121000
close(3)                                = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f96967000
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f96966000
arch_prctl(ARCH_SET_FS, 0x7f7f969666e0) = 0
mprotect(0x7f7f9611c000, 12288, PROT_READ) = 0
munmap(0x7f7f96969000, 10919)          = 0
brk(0)                                = 0x609000
brk(0x62a000)                         = 0x62a000
rt_sigaction(SIGPIPE, {SIG_IGN}, NULL, 8) = 0
open("/etc/vz/vz.conf", O_RDONLY)      = 3
stat("/etc/vz/vz.conf", {st_mode=S_IFREG|0644, st_size=988, ...}) = 0
fstat(3, {st_mode=S_IFREG|0644, st_size=988, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696b000
read(3, "## Global parameters\nVIRTUOZZO=y"..., 4096) = 988
read(3, "", 4096)                     = 0
close(3)                              = 0
munmap(0x7f7f9696b000, 4096)          = 0
open("/var/log/vzctl.log", O_WRONLY|O_CREAT|O_APPEND, 0666) = 3
fstat(3, {st_mode=S_IFREG|0644, st_size=284098, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696b000
fstat(3, {st_mode=S_IFREG|0644, st_size=284098, ...}) = 0
lseek(3, 284098, SEEK_SET)             = 284098
stat("/etc/vz/conf/118.conf", {st_mode=S_IFREG|0644, st_size=1852, ...}) = 0
open("/etc/vz/conf/118.conf", O_RDONLY) = 4
stat("/etc/vz/conf/118.conf", {st_mode=S_IFREG|0644, st_size=1852, ...}) = 0
fstat(4, {st_mode=S_IFREG|0644, st_size=1852, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696a000
read(4, "# THIS FILE IS MANAGED BY BCFG2."..., 4096) = 1852
read(4, "", 4096)                     = 0
close(4)                              = 0
munmap(0x7f7f9696a000, 4096)          = 0
fcntl(0, F_GETFL)                     = 0x8002 (flags O_RDWR|O_LARGEFILE)

```

```

fcntl(1, F_GETFL)                = 0x8002 (flags O_RDWR|O_LARGEFILE)
fcntl(2, F_GETFL)                = 0x8002 (flags O_RDWR|O_LARGEFILE)
open("/dev/vzctl", O_RDWR)        = 4
ioctl(4, 0x400c2e05, 0x7fff32fd2070) = 0
close(3)                          = 0
munmap(0x7f7f9696b000, 4096)      = 0
ioctl(4, 0x400c2e05, 0x7fff32fd2080) = 0
pipe([3, 5])                      = 0
pipe([6, 7])                      = 0
pipe([8, 9])                      = 0
pipe([10, 11])                   = 0
syscall_501(0x76, 0x60a2a0, 0xffffffffffff, 0x609fa0, 0, 0x60ac10, 0x76, 0x76, 0x76, 0x76, 0x76,
0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76, 0x76,
0x76, 0x76, 0x76, 0x76, 0x76) = 0
socket(PF_FILE, SOCK_STREAM, 0)    = 12
fcntl(12, F_SETFL, O_RDWR|O_NONBLOCK) = 0
connect(12, {sa_family=AF_FILE, path="/var/run/nscd/socket"}, 110) = 0
sendto(12, "\2\0\0\0\0\0\0\0\7\0\0\0passwd\0", 19, MSG_NOSIGNAL, NULL, 0) = 19
poll([{fd=12, events=POLLIN|POLLERR|POLLHUP, revents=POLLIN|POLLHUP}], 1, 5000) = 1
recvmsg(12, {msg_name(0)=NULL, msg_iov(2)=[{"passwd\0", 7}, {"\270O\3\0\0\0\0", 8}],
msg_controllen=24, {cmsg_len=20, cmsg_level=SOL_SOCKET, cmsg_type=SCM_RIGHTS,
{13}}, msg_flags=0x40000000 /* MSG_??? */}, 0x40000000 /* MSG_??? */) = 15
mmap(NULL, 217016, PROT_READ, MAP_SHARED, 13, 0) = 0x7f7f96931000
close(13)                         = 0
close(12)                         = 0
socket(PF_FILE, SOCK_STREAM, 0)    = 12
fcntl(12, F_SETFL, O_RDWR|O_NONBLOCK) = 0
connect(12, {sa_family=AF_FILE, path="/var/run/nscd/socket"}, 110) = 0
sendto(12, "\2\0\0\0\0\0\0\0\6\0\0\0group\0", 18, MSG_NOSIGNAL, NULL, 0) = 18
poll([{fd=12, events=POLLIN|POLLERR|POLLHUP, revents=POLLIN|POLLHUP}], 1, 5000) = 1
recvmsg(12, {msg_name(0)=NULL, msg_iov(2)=[{"group\0", 6}, {"\270O\3\0\0\0\0", 8}],
msg_controllen=24, {cmsg_len=20, cmsg_level=SOL_SOCKET, cmsg_type=SCM_RIGHTS,
{13}}, msg_flags=0x40000000 /* MSG_??? */}, 0x40000000 /* MSG_??? */) = 14
mmap(NULL, 217016, PROT_READ, MAP_SHARED, 13, 0) = 0x7f7f968fc000
close(13)                         = 0
close(12)                         = 0
rt_sigaction(SIGCHLD, {0x402d00, [], SA_RESTORER|SA_NOCLDSTOP, 0x7f7f95df6100},
NULL, 8) = 0
rt_sigaction(SIGPIPE, {SIG_IGN}, NULL, 8) = 0
rt_sigaction(SIGWINCH, {0x402d10, [], SA_RESTORER, 0x7f7f95df6100}, NULL, 8) = 0
clone(child_stack=0, flags=CLONE_CHILD_CLEARTID|CLONE_CHILD_SETTID|SIGCHLD,
child_tidptr=0x7f7f96966770) = 17613
close(3)                          = 0
close(7)                          = 0
close(9)                          = 0
close(10)                         = 0
read(8, "", 4)                    = 0
fstat(1, {st_mode=S_IFCHR|0600, st_rdev=makedev(136, 1), ...}) = 0

```

```

mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x7f7f9696b000
write(1, "entered into VE 118\n", 20)entered into VE 118
) = 20
ioctl(0, SNDCTL_TMR_TIMEBASE or TCGETS, {B38400 opost isig icanon echo ...}) = 0
ioctl(0, SNDCTL_TMR_TIMEBASE or TCGETS, {B38400 opost isig icanon echo ...}) = 0
ioctl(0, SNDCTL_TMR_STOP or TCSETSW, {B38400 -opost -isig -icanon -echo ...}) = 0
                                ioctl(0, SNDCTL_TMR_TIMEBASE or
TCGETS, {B38400 -opost -isig -icanon -echo ...}) = 0

    fcntl(0, F_GETFL)                = 0x8002 (flags O_RDWR|O_LARGEFILE)
fcntl(0, F_SETFL, O_RDWR|O_NONBLOCK|O_LARGEFILE) = 0
                                fcntl(6, F_GETFL)                = 0 (flags O_RDONLY)
                                fcntl(6, F_SETFL,
O_RDONLY|O_NONBLOCK) = 0

select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [6])

                                read(6, "\33]0;root@oudevv1: ^7", 10239) = 20
write(1, "\33]0;root@oudevv1: ^7", 20) = 20
                                select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [6])
                                read(6,
"root@oudevv1:/# ", 10239)    = 16

write(1, "root@oudevv1:/# ", 16)root@oudevv1:/# )    = 16

                                select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [0])
read(0, "\33OB", 10239)        = 3
                                write(5, "\33OB", 3)                = 3
                                select(1024, [0 6
11], NULL, NULL, NULL) = 1 (in [6])

read(6, "\7", 10239)            = 1

                                write(1, "\7", 1)                  = 1
select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [0])
                                read(0, "\33OA", 10239)              = 3
                                write(5, "\33OA", 3)                  = 3
= 3

select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [6])

                                read(6, "\7", 10239)                = 1
write(1, "\7", 1)                = 1
                                select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [0])
                                read(0, "\33OA",
10239)                            = 3

```


write(5, "\33OA", 3) = 3

select(1024, [0 6 11], NULL, NULL, NULL) = 1 (in [6])
read(6, "\7", 10239) = 1
write(1, "\7", 1) = 1
select(1024, [0 6 11], NULL,
NULL, NULL

In conclusion, I would like to mention that having replaced HOSTMINI:/etc/fstab by HOSTMINI2:/etc/fstab and rebooted HOSTMINI did not fixed the missing partitions (It's still showing just 1x 1Gb partition).

Any help would be very much appreciated at this point and keep in mind that I cannot do any dist-upgrade on any of those systems as the version of Ubuntu is very very very outdated.

Thanks for having read through all of this.
