Subject: Problems w/ busybox's init in VPS Posted by Enrico Weigelt on Tue, 27 Mar 2007 17:58:06 GMT

View Forum Message <> Reply to Message

Hi folks,

I've got problems with booting an busybox-based VPS: init does not seem to do anything (at least it does not run the boot scripts)?

Any suggest what could be wrong here?

Subject: Re: Problems w/ busybox's init in VPS
Posted by Enrico Weigelt on Tue, 27 Mar 2007 18:55:42 GMT
View Forum Message <> Reply to Message

\* Enrico Weigelt <weigelt@metux.de> wrote:

Hi,

- > I've got problems with booting an busybox-based VPS: init does
- > not seem to do anything (at least it does not run the boot
- > scripts) ?

I strace'd a little bit, and there are some strange things going on:

- \* init tries to write to fd -1! (maybe it didn't get some valid stdio passed on startup)
- \* it tries to do some tty specific ioctl()'s on fd 0, which doesn't seem to be an tty (at least it gets ENOTTY)
- \* when reading /etc/inittab, it gets fd 0, so it seems no other fd's (ie. stdin, stdout, stderr) are open!
- \* when trying to open /dev/console, it gets permission denied.

Any suggest what could be wrong here?

Subject: Re: Problems w/ busybox's init in VPS Posted by kir on Tue, 27 Mar 2007 20:13:46 GMT

View Forum Message <> Reply to Message

Let's move the discussion to devel@ list. I'm now posting to both, but please remove users@ when replying.

```
Enrico Weigelt wrote:
> * Enrico Weigelt <weigelt@metux.de> wrote:
> Hi,
>
>> I've got problems with booting an busybox-based VPS: init does
>> not seem to do anything (at least it does not run the boot
>> scripts) ?
>>
> I strace'd a little bit, and there are some strange things
> going on:
> * init tries to write to fd -1! (maybe it didn't get some
> valid stdio passed on startup)
Perhaps it tried to open /dev/console and failed (open() returned -1).
> * it tries to do some tty specific ioctl()'s on fd 0, which
  doesn't seem to be an tty (at least it gets ENOTTY)
Again that should probably be /dev/console (in case no fds are open the
first successful open() _usually_ returns 0).
> * when reading /etc/inittab, it gets fd 0, so it seems no
> other fd's (ie. stdin, stdout, stderr) are open!
```

```
This (the absense of stdin/out/err) is probably perfectly valid -- since init does not have a parent process, nobody would read/write those fds.

* when trying to open /dev/console, it gets permission denied.

Ah-ha, probably that is the root of the problem. What if you will create an empty text file named /dev/console?

Any suggest what could be wrong here?

cu
```