

---

Subject: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Mon, 23 Apr 2007 12:15:03 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

I use a CentOS 5 as HN and the OpenSuSE 10 precreated image as VE. Kernel is 2.6.18-8.el5.028stab027.1. This software is on the HN:

```
vzquota-3.0.9-1
vzyum-2.4.0-11
vzpkg-2.7.0-18
vzrpm43-python-4.3.3-7_nonptl.6
vztmpl-centos-4-2.0-2
vzctl-lib-3.0.16-1
vzctl-3.0.16-1
vzrpm44-4.4.1-22.5
vzrpm44-python-4.4.1-22.5
vzrpm43-4.3.3-7_nonptl.6
```

I can start and stop the VE from HN without any problem. Yum on HN works too. Now my problem is, that I have no connectivity at all to and from the VE (ping from HN to VE and ping from VE to HN or the internet doesn't work).

Here is my configuration:

/sbin/ifconfig -a on HN:

```
eth1    Link encap:Ethernet  HWaddr 00:14:78:06:60:A0
        inet addr:147.86.124.80  Bcast:147.86.127.255  Mask:255.255.252.0
        inet6 addr: fe80::214:78ff:fe06:60a0/64 Scope:Link
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        RX packets:300 errors:0 dropped:0 overruns:0 frame:0
        TX packets:102 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:1000
        RX bytes:29180 (28.4 KiB)  TX bytes:11179 (10.9 KiB)
        Interrupt:201 Base address:0x8c00

lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

sit0    Link encap:IPv6-in-IPv4
        NOARP  MTU:1480  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
```

collisions:0 txqueuelen:0  
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00  
inet addr:147.86.124.83 P-t-P:147.86.124.83 Bcast:147.86.127.255 Mask:255.255.252.0  
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1  
RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
collisions:0 txqueuelen:0  
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

/sbin/ifconfig -a on VE:

lo Link encap:Local Loopback  
inet addr:127.0.0.1 Mask:255.0.0.0  
inet6 addr: ::1/128 Scope:Host  
UP LOOPBACK RUNNING MTU:16436 Metric:1  
RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
collisions:0 txqueuelen:0  
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00  
inet addr:127.0.0.1 P-t-P:127.0.0.1 Bcast:0.0.0.0 Mask:255.255.255.255  
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1  
RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
collisions:0 txqueuelen:0  
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00  
inet addr:147.86.124.81 P-t-P:147.86.124.81 Bcast:0.0.0.0 Mask:255.255.255.255  
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

ifconfig -a on VE:

lo Link encap:Local Loopback  
inet addr:127.0.0.1 Mask:255.0.0.0  
inet6 addr: ::1/128 Scope:Host  
UP LOOPBACK RUNNING MTU:16436 Metric:1  
RX packets:0 errors:0 dropped:0 overruns:0 frame:0  
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0  
collisions:0 txqueuelen:0  
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

```

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
inet addr:127.0.0.1 P-t-P:127.0.0.1 Bcast:0.0.0.0 Mask:255.255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

```

```

venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
inet addr:147.86.124.81 P-t-P:147.86.124.81 Bcast:0.0.0.0 Mask:255.255.255.255
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1

```

route -n on VE:

Kernel IP routing table

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.0.2.0	0.0.0.0	255.255.255.0	U 0 0	0	0	venet0	
127.0.0.0	0.0.0.0	255.0.0.0	U 0 0	0	0	lo	

route -n on HN:

Kernel IP routing table

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
147.86.124.0	0.0.0.0	255.255.252.0	U 0 0	0	0	eth1	
147.86.124.0	0.0.0.0	255.255.252.0	U 0 0	0	0	venet0	
169.254.0.0	0.0.0.0	255.255.0.0	U 0 0	0	0	venet0	
0.0.0.0	147.86.124.1	0.0.0.0	UG 0 0	0	0	eth1	

iptables -L -vn on HN:

[CODE]

Chain INPUT (policy ACCEPT 0 packets, 0 bytes)

pkts	bytes	target	prot	opt	in	out	source	destination
614	64302	RH-Firewall-1-INPUT	all	--	*	*	0.0.0.0/0	0.0.0.0/0

Chain FORWARD (policy ACCEPT 0 packets, 0 bytes)

pkts	bytes	target	prot	opt	in	out	source	destination
0	0	RH-Firewall-1-INPUT	all	--	*	*	0.0.0.0/0	0.0.0.0/0

Chain OUTPUT (policy ACCEPT 325 packets, 37935 bytes)

pkts	bytes	target	prot	opt	in	out	source	destination
0	0	ACCEPT	all	--	lo	*	0.0.0.0/0	0.0.0.0/0
2	168	ACCEPT	icmp	--	*	*	0.0.0.0/0	0.0.0.0/0
0	0	ACCEPT	esp	--	*	*	0.0.0.0/0	0.0.0.0/0

Chain RH-Firewall-1-INPUT (2 references)

pkts	bytes	target	prot	opt	in	out	source	destination
0	0	ACCEPT	all	--	lo	*	0.0.0.0/0	0.0.0.0/0
2	168	ACCEPT	icmp	--	*	*	0.0.0.0/0	0.0.0.0/0
0	0	ACCEPT	esp	--	*	*	0.0.0.0/0	0.0.0.0/0

icmp type 255

```

0 0 ACCEPT ah -- * * 0.0.0.0/0 0.0.0.0/0
0 0 ACCEPT udp -- * * 0.0.0.0/0 224.0.0.251 udp dpt:5353
0 0 ACCEPT udp -- * * 0.0.0.0/0 0.0.0.0/0 udp dpt:631
0 0 ACCEPT tcp -- * * 0.0.0.0/0 0.0.0.0/0 tcp dpt:631
390 30609 ACCEPT all -- * * 0.0.0.0/0 0.0.0.0/0 state
RELATED,ESTABLISHED
0 0 ACCEPT tcp -- * * 0.0.0.0/0 0.0.0.0/0 state NEW tcp dpt:10000
1 48 ACCEPT tcp -- * * 0.0.0.0/0 0.0.0.0/0 state NEW tcp dpt:22
221 33477 REJECT all -- * * 0.0.0.0/0 0.0.0.0/0 reject-with
icmp-host-prohibited[/CODE]

```

iptables on VE is not running

/etc/vz/conf/12481.conf

ONBOOT="yes"

# UBC parameters (in form of barrier:limit)

# Primary parameters

AVNUMPROC="40:40"

NUMPROC="65:65"

NUMTCPSOCK="80:80"

NUMOTHERSOCK="80:80"

VMGUARPAGES="6144:2147483647"

# Secondary parameters

KMEMSIZE="2752512:2936012"

TCPSNDBUF="319488:524288"

TCPRCVBUF="319488:524288"

OTHERSOCKBUF="132096:336896"

DGRAMRCVBUF="132096:132096"

OOMGUARPAGES="6144:2147483647"

# Auxiliary parameters

LOCKEDPAGES="32:32"

SHMPAGES="8192:8192"

PRIVVMPAGES="59152:63575"

NUMFILE="2048:2048"

NUMFLOCK="100:110"

NUMPTY="16:16"

NUMSIGINFO="256:256"

DCACHESIZE="1048576:1097728"

PHYSPAGES="0:2147483647"

NUMIPTENT="128:128"

# Disk quota parameters (in form of softlimit:hardlimit)

DISKSPACE="1048576:1153434"

```
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="opensuse-10-i386-default"
ORIGIN_SAMPLE="vps.basic"
IP_ADDRESS="147.86.124.81"
HOSTNAME="12481.fhnw.ch"
```

/etc/vz/vz.conf:

```
## Global parameters
VIRTUOZZO=yes
LOCKDIR=/vz/lock
DUMPDIR=/vz/dump
VE0CPUUNITS=1000
```

```
## Logging parameters
LOGGING=yes
LOGFILE=/var/log/vzctl.log
LOG_LEVEL=0
VERBOSE=0
```

```
## Disk quota parameters
DISK_QUOTA=yes
VZFASTBOOT=no
```

```
# The name of the device whose ip address will be used as source ip for VE.
# By default automatically assigned.
#VE_ROUTE_SRC_DEV="eth0"
```

```
## Template parameters
TEMPLATE=/vz/template
```

```
## Defaults for VEs
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="vps.basic"
DEF_OSTEMPLATE="fedora-core-4"
```

```
## Load vzwdog module
```

VZWDOG="no"  
IPV6="no"

IPTABLES="ipt\_REJECT ipt\_tos ipt\_limit ipt\_multiport iptable\_filter iptable\_mangle ipt\_TCPMSS  
ipt\_tcpmss ipt\_ttl ipt\_length"

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [Vasily Tarasov](#) on Mon, 23 Apr 2007 17:52:20 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Hello,

I looked through your settings and some things are really strange for me. For example IP address of venet device on HN - no of OpenVZ scripts/tools set an IP address on it... So I want to ask you, how did you set up network? Did you do it manually? What exact commands did you use?

And the second question: please, try to turn off iptables at all for the beginning and ping HN from VE and on the contrary.

Thanks,  
Vasily.

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Wed, 25 Apr 2007 13:15:42 GMT  
[View Forum Message](#) <> [Reply to Message](#)

OK, I reinstalled the CentOS5 server this time more standard compliant

The OpenSuSE precreated VE is running now, and I can ping to HN from VE and to VE from HN. Pinging to google.com from VE is not possible though.

Here are my new specs:

/sbin/ifconfig -a on HN:

```
eth0  Link encap:Ethernet  HWaddr 00:C0:9F:45:88:12
      inet addr:147.86.124.80  Bcast:147.86.127.255  Mask:255.255.252.0
      inet6 addr: fe80::2c0:9fff:fe45:8812/64  Scope:Link
      UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
      RX packets:1905 errors:0 dropped:0 overruns:0 frame:0
      TX packets:1012 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:100
      RX bytes:232625 (227.1 KiB)  TX bytes:447344 (436.8 KiB)
```

Base address:0xece0 Memory:fe2e0000-fe300000

```
lo    Link encap:Local Loopback
      inet addr:127.0.0.1  Mask:255.0.0.0
      inet6 addr: ::1/128 Scope:Host
      UP LOOPBACK RUNNING  MTU:16436  Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

sit0  Link encap:IPv6-in-IPv4
      NOARP  MTU:1480  Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
      UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
      RX packets:36 errors:0 dropped:0 overruns:0 frame:0
      TX packets:29 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:1824 (1.7 KiB)  TX bytes:2292 (2.2 KiB)

/sbin/ifconfig -a on VE:
lo    Link encap:Local Loopback
      inet addr:127.0.0.1  Mask:255.0.0.0
      inet6 addr: ::1/128 Scope:Host
      UP LOOPBACK RUNNING  MTU:16436  Metric:1
      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
      inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.255
      UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
      RX packets:41 errors:0 dropped:0 overruns:0 frame:0
      TX packets:48 errors:0 dropped:0 overruns:0 carrier:0
      collisions:0 txqueuelen:0
      RX bytes:3204 (3.1 Kb)  TX bytes:2400 (2.3 Kb)

venet0:0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
      inet addr:147.86.124.81  P-t-P:147.86.124.81  Bcast:0.0.0.0  Mask:255.255.255.255
      UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
```

route -n on VE:

Kernel IP routing table

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.0.2.0	0.0.0.0	255.255.255.0	U 0	0	0	0	venet0
127.0.0.0	0.0.0.0	255.0.0.0	U 0	0	0	0	lo
0.0.0.0	192.0.2.1	0.0.0.0	UG 0	0	0	0	venet0

route -n on HN:

Kernel IP routing table

Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
147.86.124.81	0.0.0.0	255.255.255.255	UH 0	0	0	0	venet0
147.86.124.0	0.0.0.0	255.255.252.0	U 0	0	0	0	eth0
169.254.0.0	0.0.0.0	255.255.0.0	U 0	0	0	0	eth0
0.0.0.0	147.86.124.1	0.0.0.0	UG 0	0	0	0	eth0

iptables -L -vn on HN:

Chain INPUT (policy ACCEPT 0 packets, 0 bytes)

pkts	bytes	target	prot	opt	in	out	source	destination
1824	227K	RH-Firewall-1-INPUT	all	--	*	*	0.0.0.0/0	0.0.0.0/0

Chain FORWARD (policy ACCEPT 0 packets, 0 bytes)

pkts	bytes	target	prot	opt	in	out	source	destination
54	2688	RH-Firewall-1-INPUT	all	--	*	*	0.0.0.0/0	0.0.0.0/0

Chain OUTPUT (policy ACCEPT 1352 packets, 466K bytes)

pkts	bytes	target	prot	opt	in	out	source	destination

Chain RH-Firewall-1-INPUT (2 references)

pkts	bytes	target	prot	opt	in	out	source	destination	
0	0	ACCEPT	all	--	lo	*	0.0.0.0/0	0.0.0.0/0	
0	0	ACCEPT	icmp	--	*	*	0.0.0.0/0	0.0.0.0/0	icmp type 255
0	0	ACCEPT	esp	--	*	*	0.0.0.0/0	0.0.0.0/0	
0	0	ACCEPT	ah	--	*	*	0.0.0.0/0	0.0.0.0/0	
0	0	ACCEPT	udp	--	*	*	0.0.0.0/0	224.0.0.251	udp dpt:5353
0	0	ACCEPT	udp	--	*	*	0.0.0.0/0	0.0.0.0/0	udp dpt:631
0	0	ACCEPT	tcp	--	*	*	0.0.0.0/0	0.0.0.0/0	tcp dpt:631
1295	90004	ACCEPT	all	--	*	*	0.0.0.0/0	0.0.0.0/0	state
RELATED,ESTABLISHED									
0	0	ACCEPT	tcp	--	*	*	0.0.0.0/0	0.0.0.0/0	state NEW tcp dpt:10000
1	48	ACCEPT	tcp	--	*	*	0.0.0.0/0	0.0.0.0/0	state NEW tcp dpt:22
582	139K	REJECT	all	--	*	*	0.0.0.0/0	0.0.0.0/0	reject-with

icmp-host-prohibited

/etc/vz/conf/12481.conf

ONBOOT="yes"

# UBC parameters (in form of barrier:limit)

# Primary parameters

AVNUMPROC="40:40"

```
NUMPROC="65:65"
NUMTCPSOCK="80:80"
NUMOTHERSOCK="80:80"
VMGUARPAGES="6144:2147483647"
# Secondary parameters
KMEMSIZE="2752512:2936012"
TCPSNDBUF="319488:524288"
TCPRCVBUF="319488:524288"
OTHERSOCKBUF="132096:336896"
DGRAMRCVBUF="132096:132096"
OOMGUARPAGES="6144:2147483647"
# Auxiliary parameters
LOCKEDPAGES="32:32"
SHMPAGES="8192:8192"
PRIVVMPAGES="49152:53575"
NUMFILE="2048:2048"
NUMFLOCK="100:110"
NUMPTY="16:16"
NUMSIGINFO="256:256"
DCACHESIZE="1048576:1097728"

PHYSPAGES="0:2147483647"
NUMIPTENT="128:128"

# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="1048576:1153434"
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="opensuse-10-i386-default"
ORIGIN_SAMPLE="vps.basic"
IP_ADDRESS="147.86.124.81"
IPTABLES="iptables_filter iptable_mangle ipt_limit ipt_multiport ipt_tos ipt_TOS ipt_REJECT
ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_LOG ipt_length ip_contrack ip_contrack_ftp ip_contrack_irc
ipt_contrack ipt_state ipt_helper iptable_nat ip_nat_ftp ip_nat_irc ipt_REDIRECT"

/etc/vz/vz.conf:
## Global parameters
VIRTUOZZO=yes
LOCKDIR=/vz/lock
DUMPDIR=/vz/dump
VE0CPUUNITS=1000

## Logging parameters
```

```
LOGGING=yes
LOGFILE=/var/log/vzctl.log
LOG_LEVEL=0
VERBOSE=0
```

```
## Disk quota parameters
DISK_QUOTA=yes
VZFASTBOOT=no
```

```
# The name of the device whose ip address will be used as source ip for VE.
# By default automatically assigned.
#VE_ROUTE_SRC_DEV="eth0"
```

```
## Template parameters
TEMPLATE=/vz/template
```

```
## Defaults for VEs
VE_ROOT=/vz/root/$VEID
VE_PRIVATE=/vz/private/$VEID
CONFIGFILE="vps.basic"
DEF_OSTEMPLATE="fedora-core-4"
```

```
## Load vzwdog module
VZWDOG="no"
IPV6="no"
```

```
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length"
```

```
/etc/resolv.conf in VE
nameserver 147.86.80.20
nameserver 147.86.80.21
nameserver 208.67.222.222
```

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 13:27:48 GMT  
[View Forum Message](#) <> [Reply to Message](#)

- 1) cat /proc/sys/net/ipv4/ip\_forward
- 2) can you ping google by IP address?
- 3) try to flush all iptables rules except NAT from VE.

Vasily.

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Wed, 25 Apr 2007 13:32:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

1) /proc/sys/net/ipv4/ip\_forward  
1

2) can you ping google by IP address?  
Yes!

3) try to flush all iptables rules except NAT from VE.

iptables is not running in the VE:

```
/usr/sbin/iptables -L -vn  
Chain INPUT (policy ACCEPT 32 packets, 2544 bytes)  
pkts bytes target prot opt in out source destination  
  
Chain FORWARD (policy ACCEPT 0 packets, 0 bytes)  
pkts bytes target prot opt in out source destination  
  
Chain OUTPUT (policy ACCEPT 33 packets, 1816 bytes)  
pkts bytes target prot opt in out source destination
```

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 13:46:45 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

And how do you assign VE a nameserver? You should use `vzctl set <veid> --nameserver <nameserver_ip>`, rather when modifying `/etc/resolv.conf` in VE.

Please also provide  
`iptables -t nat -L -nv`  
output.

Thanks.

---

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Wed, 25 Apr 2007 13:50:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

`iptables -t nat -L -nv` in HN:

Chain PREROUTING (policy ACCEPT 0 packets, 0 bytes)  
pkts bytes target prot opt in out source destination

Chain POSTROUTING (policy ACCEPT 0 packets, 0 bytes)  
pkts bytes target prot opt in out source destination

Chain OUTPUT (policy ACCEPT 0 packets, 0 bytes)  
pkts bytes target prot opt in out source destination

---

Subject: Re: OpenSuSE precreated no connectiviy  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 13:57:51 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Ahem, I see that in your VE config file there is no NAMESERVER parameter! You should use  
vzctl set <veid> --nameserver <NS> --save  
command in order to set nameserver for VE!

Vasily.

---

Subject: Re: OpenSuSE precreated no connectiviy  
Posted by [goeldi](#) on Wed, 25 Apr 2007 14:04:31 GMT  
[View Forum Message](#) <> [Reply to Message](#)

OK:

/etc/vz/conf/481.conf now:

ONBOOT="yes"

# UBC parameters (in form of barrier:limit)

# Primary parameters

AVNUMPROC="40:40"

NUMPROC="65:65"

NUMTCPSOCK="80:80"

NUMOTHERSOCK="80:80"

VMGUARPAGES="6144:2147483647"

# Secondary parameters

KMEMSIZE="2752512:2936012"

TCPSNDBUF="319488:524288"

TCPRCVBUF="319488:524288"

OTHERSOCKBUF="132096:336896"

DGRAMRCVBUF="132096:132096"

OOMGUARPAGES="6144:2147483647"

```
# Auxiliary parameters
LOCKEDPAGES="32:32"
SHMPAGES="8192:8192"
PRIVVMPAGES="49152:53575"
NUMFILE="2048:2048"
NUMFLOCK="100:110"
NUMPTY="16:16"
NUMSIGINFO="256:256"
DCACHESIZE="1048576:1097728"

PHYSPAGES="0:2147483647"
NUMIPTENT="128:128"

# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="1048576:1153434"
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="opensuse-10-i386-default"
ORIGIN_SAMPLE="vps.basic"
IP_ADDRESS="147.86.124.81"
IPTABLES="iptables_filter iptable_mangle ipt_limit ipt_multiport ipt_tos ipt_TOS ipt_REJECT
iptables_tcpmss ipt_tcpmss ipt_ttl ipt_LOG ipt_length ip_contrack ip_contrack_ftp ip_contrack_irc
iptables_state ipt_helper iptable_nat ip_nat_ftp ip_nat_irc ipt_REDIRECT"

NAMESERVER="208.67.222.222"
```

Still cannot ping to domain names, pinging to ips works.

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 14:10:38 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Can you ping DNS server IP address from VE? Do you use the same DNS for HN and for VE?  
Can you give me an access to the node?

Vasily.

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [goeldi](#) on Wed, 25 Apr 2007 14:16:13 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

ping DNS: yes

same DNS: yes

access: Unfortunately not accessible from outside

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 14:28:33 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hmm. And what output  
nslookup google.com  
in VE?

Thanks,  
Vasily.

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [goeldi](#) on Wed, 25 Apr 2007 14:43:14 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

nslookup google.com  
;; connection timed out; no servers could be reached

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 14:59:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

What about two consequent commands:

```
nslookup google.com 208.67.222.222
nslookup google.com 195.85.81.128
```

please, do them on HN \_and\_ in VE too.

---

---

Subject: Re: OpenSuSE precreated no connectivi  
Posted by [goeldi](#) on Wed, 25 Apr 2007 15:06:01 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

nslookup google.com 208.67.222.222 on HN:

---

Server: 208.67.222.222  
Address: 208.67.222.222#53

Non-authoritative answer:

Name: google.com  
Address: 72.14.207.99  
Name: google.com  
Address: 64.233.187.99  
Name: google.com  
Address: 64.233.167.99

nslookup google.com 195.85.81.128 on HN:  
;; connection timed out; no servers could be reached

nslookup google.com 208.67.222.222 on VE:  
;; connection timed out; no servers could be reached

nslookup google.com 195.85.81.128 on VE:  
;; connection timed out; no servers could be reached

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 15:19:09 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Seems that there is a firewall on 208.67.222.222 or on some node between your HN and DNS.  
Can you check that?

For example you can stop all VEs, change IP address of your HN (147.86.124.80) to  
147.86.124.81 temporary (VE's current IP) and try to do  
nslookup google.com 208.67.222.222  
on HN again.

Thanks/

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Wed, 25 Apr 2007 15:31:43 GMT  
[View Forum Message](#) <> [Reply to Message](#)

There are 2 internal DNS which I tried in HN and VE: same effect. There is no Firewall between  
those DNS and this machine.

nslookup google.com 208.67.222.222 from HN when HN is .124.81 works perfect.

The two internal DNS I tried are 147.86.80.20 and 147.86.80.21.

---

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [Vasily Tarasov](#) on Wed, 25 Apr 2007 15:51:45 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Ohhh... Something strange is happening in this world! =)

Ok, please, do the following: stop all VEs except the one in question. Start "tcpdump -n -i venet0" on HN and after that do "nslookup google.com 208.67.222.222" on HN. Then post the output of tcpdump here.

Thanks.

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Fri, 27 Apr 2007 06:25:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

tcpdump gives no output when I do that, except of this message at start time:

```
tcpdump: WARNING: arptype 65535 not supported by libpcap - falling back to cooked socket
tcpdump: WARNING: venet0: no IPv4 address assigned
tcpdump: verbose output suppressed, use -v or -vv for full protocol decode
listening on venet0, link-type LINUX_SLL (Linux cooked), capture size 96 bytes
```

BTW: I had to change /etc/sysconfig/network-scripts/ifcfg-venet0 from BOOTPROTO=dhcp to BOOTPROTO=static

---

Subject: Re: OpenSuSE precreated no connectivity  
Posted by [goeldi](#) on Fri, 27 Apr 2007 06:52:12 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Now it works, when I boot with a deactivated iptables. When I boot WITH iptables enabled and stop it afterwards, it doesn't. I think there is an issue with ip\_contracks which is not cleanly unloaded. Problem is: when I start iptables, it tells me:

```
/sbin/service iptables start
Flushing firewall rules:                [ OK ]
Setting chains to policy ACCEPT: mangle filter [ OK ]
Unloading iptables modules:             [FAILED]
Applying iptables firewall rules:       [ OK ]
Loading additional iptables modules: ip_contrack_netbios_n[ OK ]
```

When I stop it:

```
/sbin/service iptables stop
Flushing firewall rules:          [ OK ]
Setting chains to policy ACCEPT: mangle filter      [ OK ]
Unloading iptables modules:      [FAILED]
```

dmesg:

```
ip_conntrack: parameter ip_conntrack_enable_ve0 is obsoleted. In ovzkernel >= 2.6.15
connection tracking on hardware node is enabled by default, use ip_conntrack_disable_ve0=1
parameter to disable.
```

```
ip_conntrack version 2.4 (8190 buckets, 65520 max) - 232 bytes per conntrack
```

```
VE: 481: started
```

```
eth0: no IPv6 routers present
```

```
lo: Disabled Privacy Extensions
```

And I get sporadic kernel panics:

## File Attachments

---

1) [Kernel\\_Panic.jpg](#), downloaded 1067 times

---

---

Subject: Re: OpenSuSE precreated no connectivi

Posted by [Vasily Tarasov](#) on Sat, 28 Apr 2007 06:08:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Thank you for investigating, can you fill two bugs, please:

1st: if iptables are loaded during start up then DNS doesn't work after rules are flushed. Please, don't forget to add there information about kernel version and `_rules_` that are in iptables on startup!

2nd: with kernel crash and when it happens.

Thank you,  
your help is very appreciated,  
Vasily

---