

---

Subject: using cdrom from inside VE

Posted by [goeldi](#) on Mon, 14 May 2007 07:45:59 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I followed instructions in the manual page 66 (--devices b:3:0:r --save) for this, but the cdrom does not show up inside the ve. These are my versions:

HN: kernel 2.6.9-023stab043.2-smp on CentOS4

VE: SuSE ELS 10

ls -l /dev/hda (this is the cdrom):

```
brw-rw---- 1 root disk 3, 0 May  2 11:18 /dev/hda
```

my 482.conf contains:

```
DEVICES="b:3:0:r "
```

I restarted VE 482. This is my /dev inside VE:

```
# ls -l /dev
```

```
total 0
```

```
crw----- 1 root root  5,  1 Jun 16 2006 console
lrwxrwxrwx 1 root root    11 May 14 09:28 core -> /proc/kcore
lrwxrwxrwx 1 root root    13 May 14 09:28 fd -> /proc/self/fd
crw----- 1 root root 10, 200 Jun 16 2006 fwmonitor
crw-rw---- 1 root root 89,  0 Jun 16 2006 i2c-0
prw----- 1 root root    0 May 14 09:28 initctl
crw----- 1 root root  1, 11 Jun 16 2006 kmsg
brw-r----- 1 root disk  9,  0 Jun 16 2006 md0
brw-r----- 1 root disk  9,  1 Jun 16 2006 md1
brw-r----- 1 root disk  9, 10 Jun 16 2006 md10
brw-r----- 1 root disk  9, 11 Jun 16 2006 md11
brw-r----- 1 root disk  9, 12 Jun 16 2006 md12
brw-r----- 1 root disk  9, 13 Jun 16 2006 md13
brw-r----- 1 root disk  9, 14 Jun 16 2006 md14
brw-r----- 1 root disk  9, 15 Jun 16 2006 md15
brw-r----- 1 root disk  9, 16 Jun 16 2006 md16
brw-r----- 1 root disk  9, 17 Jun 16 2006 md17
brw-r----- 1 root disk  9, 18 Jun 16 2006 md18
brw-r----- 1 root disk  9, 19 Jun 16 2006 md19
brw-r----- 1 root disk  9,  2 Jun 16 2006 md2
brw-r----- 1 root disk  9, 20 Jun 16 2006 md20
brw-r----- 1 root disk  9, 21 Jun 16 2006 md21
brw-r----- 1 root disk  9, 22 Jun 16 2006 md22
brw-r----- 1 root disk  9, 23 Jun 16 2006 md23
brw-r----- 1 root disk  9, 24 Jun 16 2006 md24
brw-r----- 1 root disk  9, 25 Jun 16 2006 md25
brw-r----- 1 root disk  9, 26 Jun 16 2006 md26
brw-r----- 1 root disk  9, 27 Jun 16 2006 md27
brw-r----- 1 root disk  9, 28 Jun 16 2006 md28
```

```

brw-r----- 1 root disk  9, 29 Jun 16 2006 md29
brw-r----- 1 root disk  9,  3 Jun 16 2006 md3
brw-r----- 1 root disk  9, 30 Jun 16 2006 md30
brw-r----- 1 root disk  9, 31 Jun 16 2006 md31
brw-r----- 1 root disk  9,  4 Jun 16 2006 md4
brw-r----- 1 root disk  9,  5 Jun 16 2006 md5
brw-r----- 1 root disk  9,  6 Jun 16 2006 md6
brw-r----- 1 root disk  9,  7 Jun 16 2006 md7
brw-r----- 1 root disk  9,  8 Jun 16 2006 md8
brw-r----- 1 root disk  9,  9 Jun 16 2006 md9
drwxr-xr-x 2 root root    60 Apr 20 16:23 net
crw-rw-rw- 1 root root   1,  3 Jun 16 2006 null
crw----- 1 root root 108,  0 Jun 16 2006 ppp
crw-rw-rw- 1 root tty    5,  2 May 14 09:43 ptmx
drwxr-xr-x 2 root root    0 May 14 09:28 pts
crw----- 1 root root  36,  0 Jun 16 2006 route
crw----- 1 root root 10, 135 Jun 16 2006 rtc
drwxrwxrwt 2 root root    40 Jun 16 2006 shm
crw----- 1 root root 10, 200 Jun 16 2006 skip
lrwxrwxrwx 1 root root    15 May 14 09:28 stderr -> /proc/self/fd/2
lrwxrwxrwx 1 root root    15 May 14 09:28 stdin  -> /proc/self/fd/0
lrwxrwxrwx 1 root root    15 May 14 09:28 stdout -> /proc/self/fd/1
crw-rw-rw- 1 root tty    5,  0 Jun 16 2006 tty
crw--w---- 1 root tty    4,  1 Jun 16 2006 tty1
crw----- 1 root uucp   4,  64 Jun 16 2006 ttyS0
crw----- 1 root uucp   4,  65 Jun 16 2006 ttyS1
crw----- 1 root uucp   4,  66 Jun 16 2006 ttyS2
crw----- 1 root uucp   4,  67 Jun 16 2006 ttyS3
crw----- 1 root uucp   4,  68 Jun 16 2006 ttyS4
crw----- 1 root uucp   4,  69 Jun 16 2006 ttyS5
crw----- 1 root uucp   4,  70 Jun 16 2006 ttyS6
crw----- 1 root uucp   4,  71 Jun 16 2006 ttyS7
crw----- 1 root root 10, 130 Jun 16 2006 watchdog
crw-rw-rw- 1 root root   1,  5 Jun 16 2006 zero

```

where is the cdrom?

---

Subject: Re: using cdrom from inside VE

Posted by [Vasily Tarasov](#) on Mon, 14 May 2007 09:36:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

1) `--devices b:3:0:r --save` does not create a device node in /dev. It only grants permissions to the device! You can use `--devnodes hda:r --save` command, which not only grants permissions, but also creates a node.

2) However, if you're using udev in VE (just check whether tmpfs is mounted on /dev, if it is so, then you're using udev), you need to create a device node inside VE manually once again:

```
vzctl exec <veid> mknod /dev/hda b 3 0
```

HTH,

Vasily.

---

---

Subject: Re: using cdrom from inside VE

Posted by [goeldi](#) on Mon, 14 May 2007 09:42:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

thank you, now hda shows up inside of ve.

But when I try to mount it, I get this:

```
mount: unknown filesystem type iso9660
```

---

---

Subject: Re: using cdrom from inside VE

Posted by [Vasily Tarasov](#) on Mon, 14 May 2007 10:27:11 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Ouch, I forgot you to tell you about it. This filesystem isn't virtualized, so you can't use it easily in VE. If the solution with bindmounts doesn't suite you, then you can make a tiny correction of kernel code: add to the iso9660\_fs\_type structure's fs\_flags field FS\_VIRTUALIZED flag:

```
fs_flags = FS_REQUIRES_DEV | FS_VIRTUALIZED
```

and then recompile the kernel manually.

Actually we have a enhancement bug at bugzilla: [http://bugzilla.openvz.org/show\\_bug.cgi?id=559](http://bugzilla.openvz.org/show_bug.cgi?id=559)

After fixing this bug it'll be possible to add a wishful filesystem to VE very easy:

```
vzctl set <veid> --addfs iso9660
```

But it isn't fixed now

Thanks,

Vasily.

---