Subject: Incorrect load average Posted by sspt on Sun, 30 Sep 2007 12:19:37 GMT View Forum Message <> Reply to Message

The host load average seems to be a sum of the VPS laverage:

[root@xx ~]# vzlist -o laverage,cpulimit LAVERAGE CPULIM 0.00/0.00/0.00 0 0.00/0.00/0.00 0 3.54/2.82/1.79 26 0.00/0.00/0.00 0 0.00/0.00/0.00 0

top - 05:12:05 up 15 days, 19:49, 1 user, load average: 3.56, 2.82, 1.78 Tasks: 291 total, 3 running, 288 sleeping, 0 stopped, 0 zombie Cpu(s): 0.2%us, 6.3%sy, 0.0%ni, 92.9%id, 0.1%wa, 0.0%hi, 0.5%si, 0.0%st Mem: 8140924k total, 6908692k used, 1232232k free, 647508k buffers Swap: 2031608k total, 28k used, 2031580k free, 5522328k cached

When we limit the cpu the host load average gets higher top - 05:12:05 up 15 days, 19:49, 1 user, load average: 3.56, 2.82, 1.78 but the real usage get's lower (as it should) Cpu(s): 0.2%us, 6.3%sy, 0.0%ni, 92.9%id, 0.1%wa, 0.0%hi, 0.5%si, 0.0%st

Shouldn't the host load average be calculated based on the host stats instead of the vps stats?

Subject: Re: Incorrect load average Posted by rickb on Mon, 01 Oct 2007 18:12:28 GMT View Forum Message <> Reply to Message

HN Load avg is the number of procs in the runqueue. If a VE has a very low cpulimit, it can have a high load despite low amounts of work being done (high amount of idle cpu %). Due to this, the HN load can be very deceiving.

For example- take a VE, set cpulimit to 2, start it, and run 100 cpuburn processes inside. now look at you HN's load and also the idle/user cpu %. you will see the cpus are doing almost nothing yet the load is around 100.

Rick