
Subject: [PATCH net-2.6.25 3/3] Uninline the inet_twsk_put function

Posted by [Pavel Emelianov](#) on Wed, 19 Dec 2007 10:56:13 GMT

[View Forum Message](#) <> [Reply to Message](#)

This one is not that big, but is widely used: saves 1200 bytes from net/ipv4/built-in.o

add/remove: 1/0 grow/shrink: 1/12 up/down: 97/-1300 (-1203)

function	old	new	delta
inet_twsk_put	-	87	+87
__inet_lookup_listener	274	284	+10
tcp_sacktag_write_queue	2255	2254	-1
tcp_time_wait	482	411	-71
__inet_check_established	796	722	-74
tcp_v4_err	973	898	-75
__inet_twsk_kill	230	154	-76
inet_twsk_deschedule	180	103	-77
tcp_v4_do_rcv	462	384	-78
inet_hash_connect	686	607	-79
inet_twdr_do_twkill_work	236	150	-86
inet_twdr_twcald_tick	395	307	-88
tcp_v4_rcv	1744	1480	-264
tcp_timewait_state_process	975	644	-331

Export it for ipv6 module.

Signed-off-by: Pavel Emelianov <xemul@openvz.org>

include/net/inet_timewait_sock.h | 14 +-----
net/ipv4/inet_timewait_sock.c | 15 ++++++
2 files changed, 16 insertions(+), 13 deletions(-)

diff --git a/include/net/inet_timewait_sock.h b/include/net/inet_timewait_sock.h
index abaff05..67e9250 100644

```
--- a/include/net/inet_timewait_sock.h  
+++ b/include/net/inet_timewait_sock.h  
@@ -193,19 +193,7 @@ static inline __be32 inet_rcv_saddr(const struct sock *sk)  
    inet_sk(sk)->rcv_saddr : inet_twsk(sk)->tw_rcv_saddr;  
}
```

```
-static inline void inet_twsk_put(struct inet_timewait_sock *tw)  
-  
- {  
-     if (atomic_dec_and_test(&tw->tw_refcnt)) {  
-         struct module *owner = tw->tw_prot->owner;  
-         twsk_destructor((struct sock *)tw);  
-#ifdef SOCK_REFCNT_DEBUG  
-         printk(KERN_DEBUG "%s timewait_sock %p released\n",
```

```

-     tw->tw_prot->name, tw);
-#endif
- kmem_cache_free(tw->tw_prot->tws_k_prot->tws_k_slab, tw);
- module_put(owner);
- }
-}
+extern void inet_tws_k_put(struct inet_timewait_sock *tw);

extern struct inet_timewait_sock *inet_tws_k_alloc(const struct sock *sk,
        const int state);
diff --git a/net/ipv4/inet_timewait_sock.c b/net/ipv4/inet_timewait_sock.c
index d43e787..1b7db42 100644
--- a/net/ipv4/inet_timewait_sock.c
+++ b/net/ipv4/inet_timewait_sock.c
@@ -48,6 +48,21 @@ static void __inet_tws_k_kill(struct inet_timewait_sock *tw,
    inet_tws_k_put(tw);
    }

+void inet_tws_k_put(struct inet_timewait_sock *tw)
+{
+ if (atomic_dec_and_test(&tw->tw_refcnt)) {
+ struct module *owner = tw->tw_prot->owner;
+ tws_k_destructor((struct sock *)tw);
+#ifdef SOCK_REFCNT_DEBUG
+ printk(KERN_DEBUG "%s timewait_sock %p released\n",
+     tw->tw_prot->name, tw);
+#endif
+ kmem_cache_free(tw->tw_prot->tws_k_prot->tws_k_slab, tw);
+ module_put(owner);
+ }
+}
+EXPORT_SYMBOL_GPL(inet_tws_k_put);
+
+/*
+ * Enter the time wait state. This is called with locally disabled BH.
+ * Essentially we whip up a timewait bucket, copy the relevant info into it
+ */
--
1.5.3.4

```

Subject: Re: [PATCH net-2.6.25 3/3] Uninline the inet_tws_k_put function
 Posted by [Ingo Oeser](#) on Thu, 20 Dec 2007 18:32:45 GMT
[View Forum Message](#) <> [Reply to Message](#)

Pavel Emelyanov schrieb:

```

> This one is not that big, but is widely used: saves 1200 bytes
> from net/ipv4/built-in.o
> +void inet_tws_k_put(struct inet_timewait_sock *tw)

```

```

> +{
> + if (atomic_dec_and_test(&tw->tw_refcnt)) {
> + struct module *owner = tw->tw_prot->owner;
> + twsk_destructor((struct sock *)tw);
> + #ifdef SOCK_REFCNT_DEBUG
> + printk(KERN_DEBUG "%s timewait_sock %p released\n",
> + tw->tw_prot->name, tw);
> + #endif
> + kmem_cache_free(tw->tw_prot->twsk_prot->twsk_slab, tw);
> + module_put(owner);
> + }
> +}
> +EXPORT_SYMBOL_GPL(inet_twsk_put);

```

More correct fix seems to be conversion to kref.

Just create out of line inet_twsk_release() containing sth. similiar to the code inside these braces and modify inet_twsk_put() to sth. like this:

```

static inline inet_twsk_put(struct inet_timewait_sock *tw)
{
    kref_put(&tw->kref, inet_twsk_release);
}

```

David, can you see any reason (e.g. some crazy lock stuff) NOT to do this?

Best Regards

Ingo Oeser

Subject: Re: [PATCH net-2.6.25 3/3] Uninline the inet_twsk_put function

Posted by [davem](#) on Thu, 20 Dec 2007 23:33:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

From: Pavel Emelyanov <xemul@openvz.org>

Date: Wed, 19 Dec 2007 13:56:13 +0300

```

> This one is not that big, but is widely used: saves 1200 bytes
> from net/ipv4/built-in.o
>
> add/remove: 1/0 grow/shrink: 1/12 up/down: 97/-1300 (-1203)
> function          old  new  delta
> inet_twsk_put      -   87   +87
> __inet_lookup_listener 274 284  +10
> tcp_sacktag_write_queue 2255 2254  -1

```

```
> tcp_time_wait          482  411  -71
> __inet_check_established 796  722  -74
> tcp_v4_err             973  898  -75
> __inet_twsk_kill       230  154  -76
> inet_twsk_deschedule   180  103  -77
> tcp_v4_do_rcv          462  384  -78
> inet_hash_connect      686  607  -79
> inet_twdr_do_twkill_work 236  150  -86
> inet_twdr_twcal_tick   395  307  -88
> tcp_v4_rcv             1744 1480 -264
> tcp_timewait_state_process 975  644 -331
>
> Export it for ipv6 module.
>
> Signed-off-by: Pavel Emelyanov <xemul@openvz.org>
```

Applied, thanks.

Subject: Re: [PATCH net-2.6.25 3/3] Uninline the inet_twsk_put function
Posted by [davem](#) on Fri, 21 Dec 2007 00:08:40 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Ingo Oeser <netdev@axxee.de>
Date: Thu, 20 Dec 2007 19:32:45 +0100

```
> static inline inet_twsk_put(struct inet_timewait_sock *tw)
> {
>     kref_put(&tw->kref, inet_twsk_release);
> }
>
> David, can you see any reason (e.g. some crazy lock stuff) NOT to do this?
```

Look at how this datastructure actually works before making such suggestions, don't just look at the context provided purely by a patch.

"inet_timewait_sock" begins with a "struct sock_common" which is where the atomic_t is, and:

```
#define tw_refcnt __tw_common.skc_refcnt
```

So you would have to change struct sock_common over to kref, and thus the entire networking, in order to make such a change.

I see zero value in this. There are millions of more useful things to invest that kind of time on.

But you would have seen this instantly if you had spent 5 seconds looking at how these datastructures are defined. Instead you choose to make me do it and explain it to you instead.

Subject: Re: [PATCH net-2.6.25 3/3] Uninline the inet_twsk_put function

Posted by [Ingo Oeser](#) on Fri, 21 Dec 2007 17:53:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi David,

David Miller schrieb:

> "inet_timewait_sock" begins with a "struct sock_common"

> which is where the atomic_t is, and:

>

> #define tw_refcnt __tw_common.skc_refcnt

>

> So you would have to change struct sock_common over to kref, and thus

> the entire networking, in order to make such a change.

Ok, that sounds too much. Many thanks for following up and taking the time to explain it.

> But you would have seen this instantly if you had spent 5 seconds

> looking at how these datastructures are defined. Instead you choose

> to make me do it and explain it to you instead.

Sorry, just matched the wrong pattern here :-)

Best Regards

Ingo Oeser
