
Subject: Arp

Posted by [incemmd](#) on Sat, 02 Aug 2008 10:20:33 GMT

[View Forum Message](#) <> [Reply to Message](#)

My VEs work well, but when i restart network service of Hardware Node, All VEs' network stop working.

I inspected traffic.

I see that, after restart host machine replies to the arp requests for its own IP.

```
arp who-has 192.168.61.30 tell 192.168.61.1
arp reply 192.168.61.1 is-at 00:1e:0b:c1:e5:42
```

But it does not reply to arp requests for VEs

```
arp who-has 192.168.61.30 tell 192.168.61.2
arp who-has 192.168.61.30 tell 192.168.61.2
arp who-has 192.168.61.30 tell 192.168.61.2
arp who-has 192.168.61.30 tell 192.168.61.2
```

When i restart VE it resolves the problem.

Also i can fix the problem by running

```
#ip neigh add proxy 192.168.61.2 dev eth0.611
```

But, there must be a simpler solution.

Do you have any definite solution?

Here is my configuration;

HN:

```
eth0 (192.168.100.109/27)
```

```
eth0.611 (192.168.61.1/27) - VLAN611
```

VE101

```
venet0:0 (192.168.61.2/27)
```

Subject: Re: Arp

Posted by [maratrus](#) on Thu, 07 Aug 2008 14:09:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

it's a known bug.

http://bugzilla.openvz.org/show_bug.cgi?id=753

please, if you want you can update it.
