
Subject: Troubleshooting VE start failure
Posted by [mperkel](#) on Fri, 15 Aug 2008 15:44:04 GMT
[View Forum Message](#) <> [Reply to Message](#)

All of a sudden I'm having problems starting VEs. I'm not sure what changed but here's what I'm seeing,

```
Warning: distribution not specified default used /etc/vz/dists/default
Starting VE ...
VE is mounted
VE start failed
VE is unmounted
```

The VEs are 64bit Fedora 8.

What I'm wondering is - how do I get more information to track this down? I haven't rebooted or restarted the VZ process because I have some critical VEs running that I don't want to risk the possibility that they won't restart.

Subject: Re: Troubleshooting VE start failure
Posted by [kenjy](#) on Fri, 15 Aug 2008 18:09:19 GMT
[View Forum Message](#) <> [Reply to Message](#)

Use umount to unlock it:

```
umount /vz/root/VEID
```

then try to start it again.

Subject: Re: Troubleshooting VE start failure
Posted by [kir](#) on Sat, 16 Aug 2008 04:44:01 GMT
[View Forum Message](#) <> [Reply to Message](#)

There are a lot of approaches...

First of all, check `dmesg | tail` for any errors. Then run `vzctl start` with `--verbose`.

Check VE config (`/etc/vz/conf/$VEID.conf`) -- there should be a usual set of parameters. From what I see you do not have `OSTEMPLATE` parameter specified -- not a problem since `vzctl` falls to default which happen to be RedHat/Fedora and this is what you're actually running but for the sake of completeness set it to `fedora-8` or `smth`.

If that won't help, issue `vzctl mount $VEID` and `cd` to `/vz/root/$VEID`. There you can see the VE

filesystem. It should look like a normal Linux/UNIX filesystem, i.e. stuff like /bin /lib /sbin /usr /proc etc.

Now you can chroot into it and run some checks:

```
chroot /vz/root/$VEID
```

```
# check all RPM packages, there should be a number of warnings but not too much
```

```
rpm -Va
```

```
# (if rpm won't start that something really bad happened to your VE)
```

```
# check /dev, there should be some basic stuff
```

```
ls -l /dev
```

```
# check logs, they might give you a clue what happened
```

```
less /var/log/messages
```

```
# check /sbin/init
```

```
ls -l /sbin/init
```

```
ldd /sbin/init # see that all libraries are resolved
```

```
# check /etc/inittab
```

```
less /etc/inittab
```

Subject: Re: Troubleshooting VE start failure

Posted by [pva0xd](#) on Sat, 23 Aug 2008 07:40:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

And while we are on topic. Is it possible to see messages from initscripts? How? If not, how do you guys debug initsystems? I have some troubles with openrc (system to manages the services, startup and shutdown of a host) and I'm sure it prints me correct error message but I don't see it...

Subject: Re: Troubleshooting VE start failure

Posted by [mperkel](#) on Sat, 23 Aug 2008 11:38:21 GMT

[View Forum Message](#) <> [Reply to Message](#)

I have to agree. I would like a vzctl option where I can start a VE and watch the init script run.

Subject: Re: Troubleshooting VE start failure

Posted by [piavlo](#) on Sat, 23 Aug 2008 21:37:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

IMHO ,in general ,each distribution should support logging the init boot process to some file. With openrc you can set rc_logger="YES" and it should log the init boot output to /var/log/rc.log (Similar to baselayout-1* with RC_BOOTLOG="yes" in /etc/rc.conf and app-admin/showconsole installed.)

However it looks like (at least for me) setting rc_logger="YES" does not work with openrc and openvz combination. I'd be glad

if you can check it /var/log/rc.log is created then you set rc_logger="YES in /etc/rc.conf in VE with openrc installed, so that i could report this bug in openrc as a common problem for all

openvz+openrc users.
