
Subject: [solved] NFS export /vz results in "Cannot allocate memory" on HN / CT0
Posted by [disaster](#) on Fri, 21 Nov 2008 12:34:59 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello!

I would like to export /vz but it does not work. I always get permission denied but in log is only written.

mountd[19291]: authenticated mount request from 192.168.0.1:729 for /vz (/vz)

Client:

mount: 192.168.0.3:/vz/ failed, reason given by server: Permission denied

But when i change /etc/export from /vz to /usr and then try to mount /usr it works fine.

Kernel is: RHEL5 2.6.18-059.6

Stefan

Subject: Re: NFS how to export /vz
Posted by [maratrus](#) on Fri, 21 Nov 2008 14:22:49 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello,

I'm afraid it is not OpenVZ specific question.

May be it's worth looking at /etc/export, /etc/hosts.deny files more carefully or restart nfs service.
By the way why do you want to export /vz partition?

Subject: Re: NFS how to export /vz
Posted by [disaster](#) on Fri, 21 Nov 2008 14:28:01 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi!

As i've written all other directories OTHER than /vz DO work fork export with SAME /etc/export only change directoryname.

But here is the file content:

/vz 192.168.0.0/255.255.255.0(rw,no_root_squash,sync,no_subtree_check)

hosts.deny is empty. Although as i've written nfsd writes: "mountd[19291]: authenticated mount

request from 192.168.0.1:729 for /vz (/vz)" if hosts.deny is the problem then it will not write this message.

I do not want to export /vz only a directory in it - but it also does not work for /vz at all.

```
cat /proc/mounts
none /sys sysfs rw 0 0
none /proc proc rw 0 0
udev /dev tmpfs rw 0 0
/dev/sda6 / xfs rw 0 0
/dev/sda6 /dev/.static/dev xfs rw 0 0
tmpfs /lib/init/rw tmpfs rw,nosuid 0 0
tmpfs /dev/shm tmpfs rw,nosuid,nodev 0 0
devpts /dev/pts devpts rw,nosuid,noexec 0 0
/dev/sda5 /boot ext2 rw 0 0
/dev/drbd0 /vz ext3 rw,data=ordered 0 0
nfsd /proc/fs/nfsd nfsd rw 0 0
/vz/private/110 /vz/root/110 simfs rw 0 0
tmpfs /vz/root/110/lib/init/rw tmpfs rw,nosuid 0 0
/proc /vz/root/110/proc proc rw,nosuid,nodev,noexec 0 0
sysfs /vz/root/110/sys sysfs rw,nosuid,nodev,noexec 0 0
varrun /vz/root/110/var/run tmpfs rw,nosuid 0 0
varlock /vz/root/110/var/lock tmpfs rw,nosuid,nodev,noexec 0 0
tmpfs /vz/root/110/dev/shm tmpfs rw,nosuid,nodev 0 0
devpts /vz/root/110/dev/pts devpts rw,nosuid,noexec 0 0
rpc_pipefs /var/lib/nfs/rpc_pipefs rpc_pipefs rw 0 0
```

An strace if rpc.mountd results in some cannot allocate memory:

```
rt_sigaction(SIGALRM, {SIG_DFL}, NULL, 8) = 0
open("/var/lib/nfs/rmtab", O_RDWR) = 11
fstat(11, {st_mode=S_IFREG|0644, st_size=330, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x2b6b2b250000
lseek(11, 0, SEEK_CUR) = 0
read(11, "192.168.0.10:192.168.0.0/255.255"... , 4096) = 330
lseek(11, 330, SEEK_SET) = 330
lseek(11, -223, SEEK_CUR) = 107
write(11, "192.168.0.1:192.168.0.0/255.255."..., 49) = 49
fdatasync(11) = 0
close(11) = 0
munmap(0x2b6b2b250000, 4096) = 0
close(10) = 0
open("/proc/net/rpc/nfsd.export/channel", O_WRONLY|O_CREAT|O_TRUNC, 0666) = 10
fstat(10, {st_mode=S_IFREG|0600, st_size=0, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
```



```
/usr 192.168.0.0/255.255.255.0(rw,no_root_squash,sync,no_subtree_check)
```

mounting:

```
fw-office:~# mount -t nfs 192.168.0.3:/usr/ /mnt/; umount /mnt/
fw-office:~# mount -t nfs 192.168.0.3:/vz/ /mnt/; umount /mnt/
mount: 192.168.0.3:/vz/ failed, reason given by server: Permission denied
umount: /mnt/: not mounted
```

log on nfs:

```
==> /var/log/daemon <==
Nov 24 08:43:18 cluster-office2 mountd[8515]: authenticated mount request from 192.168.0.1:990
for /usr (/usr)
Nov 24 08:43:19 cluster-office2 mountd[8515]: authenticated unmount request from
192.168.0.1:992 for /usr (/usr)
Nov 24 08:43:27 cluster-office2 mountd[8515]: authenticated mount request from 192.168.0.1:995
for /vz (/vz)
```

Subject: Re: NFS cannot export /vz
Posted by [disaster](#) on Mon, 24 Nov 2008 09:10:34 GMT
[View Forum Message](#) <> [Reply to Message](#)

strace of mountd

For a dir that works fine (/usr):

```
open("/proc/fs/nfsd/filehandle", O_RDWR) = 10
fstat(10, {st_mode=S_IFREG|0600, st_size=0, ...}) = 0
mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x2b50edee5000
write(10, "192.168.0.0/255.255.255.0 /usr 6"..., 35) = 35
read(10, "\x0100000000008000697080000\n", 4096) = 27
close(10) = 0
munmap(0x2b50edee5000, 4096) = 0
write(8, "\200\0\0Dr\214\207Y\0\0\0\1\0\0\0\0\0\0\0\0\0\0\0\0"..., 72) = 72
select(1024, [3 4 5 6 7 8], NULL, NULL, NULL) = 1 (in [8])
poll([{fd=8, events=POLLIN, revents=POLLIN}], 1, 35000) = 1
read(8, "", 4000) = 0
close(8) = 0
select(1024, [3 4 5 6 7], NULL, NULL, NULL)
```

for /vz dir:

if my memory does not fail me, reboot is required

Subject: Re: NFS export /vz results in "Cannot allocate memory" on HN / CT0

Posted by [disaster](#) on Mon, 24 Nov 2008 11:47:12 GMT

[View Forum Message](#) <> [Reply to Message](#)

oh thanks - OK now it works.
