
Subject: [PATCH 1/3][UNIX] Make unix_tot_inflight counter non-atomic
Posted by [Pavel Emelianov](#) on Wed, 07 Nov 2007 13:52:36 GMT
[View Forum Message](#) <> [Reply to Message](#)

This counter is `_always_` modified under the `unix_gc_lock` spinlock, so its atomicity can be provided w/o additional efforts.

Signed-off-by: Pavel Emelianov <xemul@openvz.org>

```
diff --git a/include/net/af_unix.h b/include/net/af_unix.h
index 0864a77..a1c805d 100644
```

```
--- a/include/net/af_unix.h
```

```
+++ b/include/net/af_unix.h
```

```
@@ -12,7 +12,7 @@ extern void unix_gc(void);
```

```
#define UNIX_HASH_SIZE 256
```

```
-extern atomic_t unix_tot_inflight;
```

```
+extern unsigned int unix_tot_inflight;
```

```
struct unix_address {
    atomic_t refcnt;
```

```
diff --git a/net/unix/af_unix.c b/net/unix/af_unix.c
index 515e7a6..ab9048a 100644
```

```
--- a/net/unix/af_unix.c
```

```
+++ b/net/unix/af_unix.c
```

```
@@ -457,7 +457,7 @@ static int unix_release_sock (struct sock *sk, int embrion)
```

```
    * What the above comment does talk about? --ANK(980817)
```

```
    */
```

```
- if (atomic_read(&unix_tot_inflight))
```

```
+ if (unix_tot_inflight)
```

```
    unix_gc(); /* Garbage collect fds */
```

```
    return 0;
```

```
diff --git a/net/unix/garbage.c b/net/unix/garbage.c
```

```
index 406b643..399717e 100644
```

```
--- a/net/unix/garbage.c
```

```
+++ b/net/unix/garbage.c
```

```
@@ -92,7 +92,7 @@ static LIST_HEAD(gc_inflight_list);
```

```
static LIST_HEAD(gc_candidates);
```

```
static DEFINE_SPINLOCK(unix_gc_lock);
```

```
-atomic_t unix_tot_inflight = ATOMIC_INIT(0);
```

```
+unsigned int unix_tot_inflight;
```

```
static struct sock *unix_get_socket(struct file *filp)
@@ -133,7 +133,7 @@ void unix_inflight(struct file *fp)
    } else {
        BUG_ON(list_empty(&u->link));
    }
- atomic_inc(&unix_tot_inflight);
+ unix_tot_inflight++;
    spin_unlock(&unix_gc_lock);
}
}
@@ -147,7 +147,7 @@ void unix_notinflight(struct file *fp)
    BUG_ON(list_empty(&u->link));
    if (atomic_dec_and_test(&u->inflight))
        list_del_init(&u->link);
- atomic_dec(&unix_tot_inflight);
+ unix_tot_inflight--;
    spin_unlock(&unix_gc_lock);
}
}
--
1.5.3.4
```

Subject: Re: [PATCH 1/3][UNIX] Make unix_tot_inflight counter non-atomic
Posted by [davem](#) on Sun, 11 Nov 2007 06:06:10 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Pavel Emelyanov <xemul@openvz.org>
Date: Wed, 07 Nov 2007 16:52:36 +0300

> This counter is always modified under the unix_gc_lock spinlock,
> so its atomicity can be provided w/o additional efforts.
>
> Signed-off-by: Pavel Emelyanov <xemul@openvz.org>

Applied.
